

# Hortonworks Data Platform

## Ambari Views Guide

(Aug 28, 2015)

## Hortonworks Data Platform : Ambari Views Guide

Copyright © 2012-2015 Hortonworks, Inc. All rights reserved.

The Hortonworks Data Platform, powered by Apache Hadoop, is a massively scalable and 100% open source platform for storing, processing and analyzing large volumes of data. It is designed to deal with data from many sources and formats in a very quick, easy and cost-effective manner. The Hortonworks Data Platform consists of the essential set of Apache Hadoop projects including MapReduce, Hadoop Distributed File System (HDFS), HCatalog, Pig, Hive, HBase, Zookeeper and Ambari. Hortonworks is the major contributor of code and patches to many of these projects. These projects have been integrated and tested as part of the Hortonworks Data Platform release process and installation and configuration tools have also been included.

Unlike other providers of platforms built using Apache Hadoop, Hortonworks contributes 100% of our code back to the Apache Software Foundation. The Hortonworks Data Platform is Apache-licensed and completely open source. We sell only expert technical support, [training](#) and partner-enablement services. All of our technology is, and will remain free and open source. Please visit the [Hortonworks Data Platform](#) page for more information on Hortonworks technology. For more information on Hortonworks services, please visit either the [Support](#) or [Training](#) page. Feel free to [Contact Us](#) directly to discuss your specific needs.

Licensed under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at

<http://www.apache.org/licenses/LICENSE-2.0>

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

## Table of Contents

1. Using Ambari Views .....	1
2. Preparing Ambari Server for Views .....	2
3. Running Ambari Server Standalone .....	3
3.1. Prerequisites .....	3
3.2. Standalone Server Setup .....	4
3.3. Reverse Proxy .....	4
4. Configuring Views for Kerberos .....	5
5. Using the Tez View .....	6
5.1. Configuring Your Cluster for Tez View .....	6
5.2. Creating or Editing the Tez View Instance .....	7
5.2.1. User Permissions for Tez Views .....	9
5.2.2. Kerberos Setup for Tez Views .....	10
5.3. Using the Tez View .....	10
5.3.1. Understanding Directed Acyclic Graphs (DAGs), Vertices, and Tasks.....	11
5.3.2. Identifying the Tez DAG for Your Job .....	11
5.3.3. Understanding How Your Tez Job Is Executed .....	13
5.3.4. Identifying Causes of Failed Jobs .....	14
5.3.5. Viewing All Failed Tasks .....	14
5.3.6. Using Counters to Identify the Cause of Slow-Performing Jobs .....	14
6. Using the Pig View .....	16
6.1. Configuring Your Cluster for Pig View .....	16
6.2. Creating the Pig View Instance .....	17
6.2.1. Getting Correct Configuration Values for Manually-Deployed Clusters .....	18
6.2.2. User Permissions for Pig Views .....	19
6.2.3. Kerberos Setup for Pig Views .....	20
6.3. Using the Pig View .....	21
6.3.1. Writing Pig Scripts .....	21
6.3.2. Viewing Pig Script Execution History .....	22
6.3.3. User-Defined Functions (UDFs) Tab .....	22
7. Using the Capacity Scheduler View .....	23
7.1. Configuring your Cluster for the Capacity Scheduler View .....	23
7.2. Creating a Capacity Scheduler View Instance .....	23
7.2.1. User Permissions for Capacity Scheduler Views .....	26
7.3. Using the Capacity Scheduler View .....	30
7.3.1. Setting up Queues .....	30
7.3.2. Configuring Queues .....	35
7.3.3. Configuring Cluster Scheduler Settings .....	36
7.3.4. Applying the Configuration Changes .....	37
7.4. Troubleshooting .....	38
8. Using the Hive View .....	40
8.1. Configuring Your Cluster .....	40
8.1.1. Setup HDFS Proxy User .....	40
8.1.2. Setup HDFS User Directory .....	41
8.2. Creating the Hive View Instance .....	42
8.2.1. Settings and Cluster Configuration .....	42
8.2.2. User Permissions for Hive Views .....	44
8.2.3. Kerberos Setup for Hive Views .....	44

---

8.3. Using the Hive View .....	45
8.3.1. Query Tab .....	45
8.3.2. Saved Queries Tab .....	49
8.3.3. History Tab .....	50
8.3.4. UDF Tab .....	50
8.4. Troubleshooting .....	51
9. Using the Slider View .....	52
9.1. Deploying the Slider View .....	52
10. Using the Files View .....	53
10.1. Configuring Your Cluster for Files View .....	53
10.2. Creating the Files View Instance .....	53

## List of Figures

3.1. Configuring Views with your HDP Cluster .....	3
5.1. Tez View Create Instance Page .....	7
5.2. Tez View Instance Page .....	9
5.3. Granting User Permissions to Tez Views .....	9
5.4. SQL Query Execution in Hive .....	11
5.5. Tez View Column Selector Dialog Box .....	12
5.6. View Tab in Tez View .....	13
5.7. DAG Details Window .....	14
5.8. Tez View All Tasks Tab .....	14
5.9. Tez View DAG-Level Counters Tab .....	15
5.10. Tez View Vertex-Level Counters Tab .....	15
5.11. Tez View Task-Level Counters Tab .....	15
6.1. Pig View Details and Settings .....	17
6.2. Pig View Cluster Configuration .....	18
6.3. HDFS Service Page in Ambari .....	19
6.4. Using the Filter to Search Advanced hdfs-site Settings .....	19
6.5. Granting User Permissions to Pig Views .....	20
6.6. Kerberos Settings for Pig Views .....	21
6.7. Pig Script Running in the Pig View .....	21
6.8. Pig View Script History Tab .....	22
6.9. Pig View UDFs Tab .....	22
8.1. HDFS Service Page in Ambari .....	43
8.2. Using the Filter to Search Advanced hdfs-site Settings .....	44
8.3. Granting User Permissions to Hive Views .....	44
8.4. Hive View Kerberos Configuration Example .....	45
8.5. Hive View Database Explorer .....	46
8.6. Query Editor .....	46
8.7. Query Results and Logs in Hive View Query Editor .....	47
8.8. Query Editor Textual Explain Feature .....	48
8.9. Query Editor Visual Explain Feature .....	48
8.10. Tez View Query Debugging Option .....	49
8.11. Query Editor Error Message Summary Window .....	49
8.12. Query Editor Error Message Details Window .....	49
8.13. Saved Queries Tab .....	50
8.14. History Tab .....	50
8.15. UDF Tab .....	50

## List of Tables

5.1. Cluster Configurations for Tez View .....	6
5.2. Cluster Configuration Values for the Tez View in Ambari .....	8
5.3. Kerberos Settings for Tez Views .....	10
5.4. Tez Job Status Descriptions .....	12
6.1. Finding Cluster Configuration Values for the Pig View in Ambari .....	18
6.2. Pig View Settings for NameNode High Availability .....	19
8.1. Hive View Instance Details .....	42
8.2. Finding Cluster Configuration Values for the Hive View in Ambari .....	42
8.3. Hive View Settings for NameNode High Availability .....	43
8.4. Kerberos Settings for Hive Views .....	44
8.5. Troubleshooting Hive Views Errors .....	51

# 1. Using Ambari Views

Ambari includes the [Ambari Views Framework](#), which allows for developers to create UI components that “plug into” the Ambari Web interface. Ambari includes a built-in set of Views that are pre-deployed for you to use with your cluster. This guide provides information on configuring the built-in set of Views, as well as information on how to configure Ambari Server for “standalone” operation.

Views can be deployed and managed in the “operational” Ambari Server that is operating your cluster. In addition, Views can be deployed and managed in one or more separate “standalone” Ambari Servers. Running “standalone” Ambari Server instances is useful when users who will access views will not have (and should not) have access to that Ambari Server that is operating the cluster. As well, you can run one or more separate Ambari Server instances “standalone” for a scale-out approach to handling a large number of users. See [Running Ambari Standalone](#) for more information.



## Important

It is critical that you prepare your Ambari Server for hosting views. It is strongly recommended you increase the amount of memory available to your Ambari Server, and that you run additional “standalone” Ambari Servers to host the views. See [Preparing Ambari Server for Views](#) and [Running Ambari Server Standalone](#) for more information.

View	Description	HDP Stacks	Required Services
<a href="#">Capacity Scheduler</a>	Provides a visual way to configure YARN capacity scheduler queue capacity.	HDP 2.3 or later	YARN
<a href="#">Files</a>	Allows you to browse the HDFS file system.	HDP 2.2 or later	HDFS
<a href="#">Hive</a>	Exposes a way to find, author, execute and debug Hive queries.	HDP 2.3 or later	HDFS, YARN, Hive
<a href="#">Pig</a>	Provides a way to author and execute Pig Scripts.	HDP 2.2 or later	HDFS, Hive ( WebHCat ), Pig
<a href="#">Slider</a>	A tool to help deploy and manage Slider-based applications.	HDP 2.1 or later	HDFS, YARN
<a href="#">Tez</a>	View information related to Tez jobs that are executing on the cluster.	HDP 2.2.4.2 or later	HDFS, YARN, Tez

## Learning More About Views

You can learn more about the Views Framework at the following resources:

Resource	URL
Administering Views	Ambari Administration Guide - <a href="#">Managing Views</a>
Ambari Project Wiki	<a href="https://cwiki.apache.org/confluence/display/AMBARI/Views">https://cwiki.apache.org/confluence/display/AMBARI/Views</a>
Example Views	<a href="https://github.com/apache/ambari/tree/trunk/ambari-views/examples">https://github.com/apache/ambari/tree/trunk/ambari-views/examples</a>
View Contributions	<a href="https://github.com/apache/ambari/tree/trunk/contrib/views">https://github.com/apache/ambari/tree/trunk/contrib/views</a>

## 2. Preparing Ambari Server for Views

When hosting multiple views in Ambari, it is **strongly recommended** you increase the amount of memory available available to the Ambari Server. Since each view requires it's own memory footprint, increasing the Ambari Server maximum allocable memory will help support multiple deployed views and concurrent use.

1. On the Ambari Server host, edit the `ambari-env.sh` file:

```
vi /var/lib/ambari-server/ambari-env.sh
```

2. For the `AMBARI_JVM_ARGS` variable, replace the default `-Xmx2048m` with the following:

```
-Xmx4096m -XX:PermSize=128m -XX:MaxPermSize=128m
```

3. Restart Ambari Server for this change to take effect.

```
ambari-server restart
```

## 3. Running Ambari Server Standalone

You can run one or more separate Ambari Server instances running in “standalone” mode. Running “standalone” Ambari Server instances is useful when users who will access views will not have (and should not) have access to that Ambari Server that is operating the cluster. As well, you can run one or more separate Ambari Server instances “standalone” for a scale-out approach to handling a large amount of users. See [Reverse Proxy](#) for more information.


### 3.1. Prerequisites

There are several requirements that need to be considered when setting up multiple Ambari Server “standalone” instances:

- Ambari Server instances should be the same version.
- The Ambari Server instances should point to the same underlying database.
- Ambari database should be scaled and made highly-available, independent of Ambari Server.
- If using an external authentication source (such as LDAP or Active Directory), Ambari Server authentication should be configured the same for all Ambari Server instances.
- If the cluster you are accessing with Views is Kerberos-enabled, you need to configure Ambari and the Views for Kerberos.
- Run the multiple “standalone” Ambari Server instances behind a Reverse Proxy.

After your standalone Ambari Servers are setup and configured, you can configure the views to communicate with your HDP cluster.

**Figure 3.1. Configuring Views with your HDP Cluster**



## 3.2. Standalone Server Setup

Setting up a standalone Ambari Server instance is very similar to setting up an operational Ambari Server. Many of the steps are the same, with one key **exception: you do not install a cluster with a standalone Ambari Server**. A standalone Ambari Server does not manage a cluster and does not deploy or communicate with Ambari Agents. The standalone Ambari Server runs as web server instance, serving views for users.



### Important

Refer to the [Ambari Install Guide](#) for the details steps for setting up an Ambari Server. For a standalone Ambari Server instance, you are not required to install a cluster.



### Important

Refer to [Managing Views](#) in the Ambari Administration Guide for information on deploying and configuring Views.

The following table compares the high-level tasks required to setup an operational Ambari Server vs. a standalone Ambari Server.

	Operational Ambari Server	Standalone Ambari Server
1	Install ambari -server package	Install ambari -server package
2	Run ambari -server setup (DB, JDK)	Run ambari -server setup (DB, JDK)
3	Configure external LDAP authentication	Configure external LDAP authentication
4	Install Cluster	<b>NA</b>
5	Deploy views	Deploy views
6	Create + configure view instances	Create + configure view instances
7		(Optional) Repeat for each Ambari Server instance
8		(Optional) Setup proxy for Ambari Server instances

## 3.3. Reverse Proxy

If you require a larger number of users to access Ambari Views, it may be necessary to “scale-out” the Ambari Server by installing and running multiple Ambari Server standalone instances that host Ambari Views and run those instances behind a reverse proxy.

If a reverse proxy fronts the standalone Ambari Server instances, the only requirement is that the reverse proxy honors session affinity, meaning that once a session has been established the reverse proxy routes each subsequent request to the same Ambari server instance. Depending on the reverse proxy implementation, this can be accomplished in a number of different ways, including hashing client IP and using the JSESSIONID header.



### Important

Using multiple Ambari Server instances and a reverse proxy in front of those instances is **not supported** for an operational Ambari Server. It is only supported for standalone Ambari Server instances (i.e. Ambari instances that are not managing a cluster).

## 4. Configuring Views for Kerberos

If the cluster your views will communicate with is Kerberos-enabled, you need to configure the Ambari Server instance(s) for Kerberos and be sure to configure the views to work with Kerberos.

Refer to the [Set Up Kerberos for Ambari](#) for the instructions on how to configure Ambari Server for Kerberos. Be sure to configure all standalone Ambari Server instances.



### Important

Be sure to install the Kerberos client utilities on the Ambari Server so that Ambari can kinit.

#### RHEL/CentOS/Oracle Linux

```
yum install krb5-workstation
```

#### SLES

```
zypper install krb5-client
```

Once your Ambari Server is setup for Kerberos, be sure to follow the specific instructions with each view on how to configure the view for Kerberos and the cluster for Kerberos access from the view.

## 5. Using the Tez View

Tez is an framework for building high performance batch and interactive data processing applications. Apache Hive and Pig use the Tez framework. When you run a job such as a Hive query or Pig script using Tez, you can use the Tez View to track and debug the execution of that job. Topics in this chapter describe how to configure, deploy and use the Tez View to execute jobs in your cluster:

- [Configuring Your Cluster for Tez View](#)
- [Creating the Tez View Instance](#)
- [Using the Tez View](#)

### 5.1. Configuring Your Cluster for Tez View

When you deploy a cluster with Ambari, a Tez View instance is automatically created. However, you must verify that the configurations listed in the following table have been correctly set.

If you have manually deployed your cluster, you must set the properties listed in the following table to configure your cluster before you create the Tez View on your standalone Ambari server.

**To configure your cluster for the Tez View:**

1. Confirm the following configurations are set:

**Table 5.1. Cluster Configurations for Tez View**

Component	Configuration	Property	Comments
YARN	yarn-site.xml	yarn.resourcemanager.system-metrics-publisher.enabled	Enable the generic history service in the Timeline Server. Verify that this property is set to <code>true</code> .
YARN	yarn-site.xml	yarn.timeline-service.enabled	Enable the Timeline Server for logging details. Verify that this property is set to <code>true</code> .
YARN	yarn-site.xml	yarn.timeline-service.webapp.address	Value must be the <code>IP:PORT</code> on which the Timeline Server is running.

2. If you changed any settings, you must restart the YARN ResourceManager and the Timeline Server for your changes to take effect.



#### Important

If you do not need to reconfigure the Ambari-created Tez View, see [Using the Tez View](#).

## 5.2. Creating or Editing the Tez View Instance

Depending on whether you must create a new Tez View instance for a manually deployed cluster or modify an Ambari-created Tez View, see one of the following sections:

- [Modifying a Tez View Instance on an Ambari-Managed Cluster \[7\]](#)
- [Creating a New Tez View Instance on a Manually-Deployed Cluster \[7\]](#)

**To modify a Tez View instance on an Ambari-managed cluster:**

1. Navigate to the Ambari Administration interface.
2. Click **Views** and expand the **Tez View**.
3. On the Create Instance page, change the appropriate configuration parameters.
4. Select **Local Ambari-Managed Cluster**:

**Figure 5.1. Tez View Create Instance Page**

View: TEZ  
Version: 0.7.0.2.3.0.0-2108

**Details**

Instance Name:

Display Name:

Description:

Visible

**Cluster Configuration**

Local Ambari Managed Cluster

Cluster Name: MyCluster

Custom

YARN Timeline Server URL: yarn.timeline-service.hostname:8188

YARN ResourceManager URL: yarn.resourcemanager.hostname:8088

Cancel Save



### Important

Secure clusters that use wire encryption (SSL/TSL) cannot use the **Local Ambari Managed Cluster** option. Instead you must configure the view as described in the [instructions for manually-deployed clusters \[7\]](#).

5. Click **Save**, grant Permissions on the view (see [User Permissions for Tez Views](#)), and click **Go to instance** to use the view. See [Using the Tez View](#).

**To create a new Tez View instance for a manually-deployed cluster:**

1. Navigate to the Ambari Administration interface.

2. Click **Views**, expand the **Tez View**, and click **Create Instance**.
3. On the Create Instance page, select the **Version**.
4. Enter the Details (required). The Instance Name appears in the URI, the Display Name appears in the Views drop-down list, and the Description helps multiple users identify the view.
5. Scroll down to the Cluster Configuration, verify that **Custom** is checked and enter the following values, which tell the Tez View how to access resources in the cluster:

**Table 5.2. Cluster Configuration Values for the Tez View in Ambari**

Property	Value
YARN Timeline Server URL (required)	<p>The URL to the YARN Application Timeline Server, used to provide Tez information. Typically, this is the <code>yarn.timeline-service.webapp.address</code> property that is specified in the <code>etc/hadoop/conf/yarn-site.xml</code>.</p> <p>When you enter the value in the view definition, prepend "http://" to the value you find in the <code>yarn-site.xml</code> file. For example, <code>http://&lt;timeline server host&gt;:8188</code></p> <p><b>For wire encryption-enabled clusters:</b></p> <p>Set this based on the value of <code>yarn.timeline-service.webapp.https.address</code> in <code>yarn-site.xml</code></p> <p>When you enter the value in the view definition, prepend "https://" to the value. For example, <code>https://&lt;timeline server host&gt;:8190</code></p>
YARN ResourceManager URL (required)	<p>The URL to the YARN ResourceManager, used to provide YARN Application data. Typically, this is the <code>yarn.resourcemanager.webapp.address</code> property that is specified in the <code>etc/hadoop/conf/yarn-site.xml</code>.</p> <p>When you enter the value in the view definition, prepend "http://" to the value you find in the <code>yarn-site.xml</code> file. For example, <code>http://&lt;resourcemanager host&gt;:8088</code></p> <p><b>For wire encryption-enabled clusters:</b></p> <p>Set this based on the value of <code>yarn.resourcemanager.webapp.https.address</code> in <code>yarn-site.xml</code></p> <p>When you enter the value in the view definition, prepend "https://" to the value. For example, <code>https://&lt;resourcemanager host&gt;:8090</code></p>

6. Click **Save** and grant Permissions on the view (see [User Permissions for Tez Views](#)).
7. At the top of the view instance configuration page, click **Go to instance**.
8. When your browser is at the view instance page, copy the URL for the Tez View from your browser address bar:

Figure 5.2. Tez View Instance Page



9. In `tez-site.xml`, specify the URL that you copied in Step 8 as the value for the `tez.tez-ui.history-url.base` property, and save the file.

10 Restart the HiveServer2 daemon to make sure that your changes to `tez-site.xml` take effect.

To use the view, see [Using the Tez View](#).




### Important

If your cluster is configured for Kerberos, you must set up Ambari Server for Kerberos for the Tez View to access the ATS component. See [Kerberos Setup for Tez Views](#).

## 5.2.1. User Permissions for Tez Views

After saving the Tez View instance definition, grant permission on the view for the set of users who can use the view:

Figure 5.3. Granting User Permissions to Tez Views





## Note

To grant access to all Hive and Pig users, create a group that contains these users, and then grant permission to use the Tez View to that group. See also the ["Managing Users and Groups"](#) section in the *Administering Ambari* guide.

## 5.2.2. Kerberos Setup for Tez Views

To set up basic Kerberos for views, see ["Set Up Kerberos for Ambari Server"](#) in the *Ambari Security Guide*.

After you have set up basic Kerberos for the Tez View, you must set the following configuration properties:

1. Set the following values for properties in the YARN configuration for Ambari-managed clusters or the `yarn-site.xml` for manually deployed clusters:

**Table 5.3. Kerberos Settings for Tez Views**

Property	Value
<code>yarn.timeline-service.http-authentication.proxyuser.\${ambari principal name}.hosts</code>	*
<code>yarn.timeline-service.http-authentication.proxyuser.\${ambari principal name}.users</code>	*
<code>yarn.timeline-service.http-authentication.proxyuser.\${ambari principal name}.groups</code>	*

For example, if the Kerberos principal used for the Ambari server is `ambari-service@EXAMPLE.COM`, replace `${ambari principal name}` with `ambari-service`.

2. Restart the Timeline Server so your configuration changes take effect.

## 5.3. Using the Tez View

Tez provides a framework that enables human-interactive response times with Apache Hive queries and Apache Pig data transformations. The Tez View enables you to understand and debug submitted Tez jobs, such as Hive queries or Pig scripts, that are executed using the Tez execution engine.

The following sections discuss using the Tez Views to manage Hive and Pig tasks:

- [Understanding DAGs, Vertices, and Tasks](#)
- [Identifying the Tez DAG for Your Job](#)
- [Understanding How Your Tez Job Is Executed](#)
- [Identifying Causes of Failed Jobs](#)


- [Viewing All Failed Tasks](#)
- [Using Counters to Identify the Cause of Slow-Performing Jobs](#)

### 5.3.1. Understanding Directed Acyclic Graphs (DAGs), Vertices, and Tasks

To explain DAGs, vertices, and tasks, consider how Hive SQL queries are compiled and converted into a Tez execution graph also known as a DAG. A DAG is a collection of vertices where each vertex executes a fragment of the query or script. Directed connections between vertices determine the order in which they are executed. For example, the vertex to read a table must be run before a filter can be applied to the rows of that table.

As another example, consider when a vertex reads a user table. This table can be very large and distributed across multiple computers and multiple racks. Reading the table is achieved by running many tasks in parallel. The following figure shows the execution of a SQL query in Hive:

**Figure 5.4. SQL Query Execution in Hive**



### 5.3.2. Identifying the Tez DAG for Your Job

To identify the Tez DAG for your job:

1. Navigate to the Tez View instance by clicking **Go to instance** on the Tez View page in Ambari. The Tez View instance page displays a list of jobs sorted by time, listing the latest jobs first. You can search a job using the following fields:


- **Dag Name** (DAG name for the job)
- **Id** (DAG identifier)
- **Submitter** (user who submitted the job)
- **Status** (job status)
- **Application ID**

2. When you have entered your search criteria, press **Enter**, and search results matching your criteria are returned below.

### Selecting the Columns That Appear in Search Results

To select which columns are included in the Tez View search results, click the gear icon to the right of the search tool bar. A Column Selector dialog box appears where you can select which columns appear in the search results. Select the columns, and click **Ok** to return to the Tez View:

**Figure 5.5. Tez View Column Selector Dialog Box**



### Note

To search for columns, use the search well at the top of the Column Selector dialog box. Check **Select All** to include all columns in your search results and uncheck it to clear all of your column selections.

### Understanding Tez View Job Status

The following table explains the job status field that is returned for all search results returned in the Tez View:

**Table 5.4. Tez Job Status Descriptions**

Status	Description
Submitted	The DAG is submitted to Tez but is not running.
Running	The DAG is currently running.
Succeeded	The DAG completed successfully.
Failed	The DAG failed to complete successfully.

Status	Description
Killed	The DAG was stopped manually.
Error	An internal error occurred when executing the DAG.


### 5.3.3. Understanding How Your Tez Job Is Executed

The Tez View enables you to gain insight into the complexity and the progress of executing jobs.

The View tab shows the following:

- DAG graphical view
- All vertices
- Tasks per vertex on top right of the vertex
- Failed vertices display in red, successful vertices display in green
- Mouse over vertices to view timeline details

Figure 5.6. View Tab in Tez View



The View Tab enables you to investigate the vertices that have failures or are taking a long time.

### 5.3.4. Identifying Causes of Failed Jobs

The Tez View enables you to quickly find and report errors. When a Tez task fails, you must:

- Identify why the task failed
- Capture the reason for task failure

When a Tez task fails, the DAG Details tab explains the failure:

Figure 5.7. DAG Details Window

The screenshot shows the Ambari DAG Details window for a failed task. The 'DAG Details' section includes a 'Download data' button and the following information:

- Application Id: application\_1434230750579\_0006
- Entity Id: dag\_1434230750579\_0006\_1
- User: ambari-qa
- Status: FAILED [ Failed Tasks ] [ Failed TaskAttempts ]
- Start Time: 14 Jun 2015 10:17:13
- End Time: 14 Jun 2015 10:17:23
- Duration: 9 secs

The 'Diagnostics' section shows the following error details:

```

Vertex failed, vertexName=Map 1, vertexId=vertex_1434230750579_0006_1_00, diagnostics=
> Task failed, taskId=task_1434230750579_0006_1_00_000000, diagnostics=
> TaskAttempt 0 failed, info=
  > Container container_1434230750579_0006_01_000002 finished with diagnostics set to
  > Container failed, exitCode=1, Exception from container-launch.
  Container id: container_1434230750579_0006_01_000002
  Exit code: 1
  Stack trace: ExitCodeException exitCode=1:
    at org.apache.hadoop.util.Shell.runCommand(Shell.java:545)
    at org.apache.hadoop.util.Shell.run(Shell.java:456)
    at org.apache.hadoop.util.Shell$ShellCommandExecutor.execute(Shell.java:722)
  
```

### 5.3.5. Viewing All Failed Tasks

Multiple task failures may occur. The Tez View All Tasks tab enables you to view all tasks that failed and examine the reason and logs for each failure. Logs for failed tasks, but not for aborted tasks are available to download from this tab:

Figure 5.8. Tez View All Tasks Tab

The screenshot shows the Ambari Tez View All Tasks tab. The 'All Tasks' tab is selected. The table below shows the details of a failed task:


Task Index	Vertex Name	Status	Start Time	End Time	Duration	Actions	Logs
00_000000	Map 3	FAILED	14 Jun 2015 14:44:58	14 Jun 2015 14:45:06	7 secs	counters attempts	Not Avail

### 5.3.6. Using Counters to Identify the Cause of Slow-Performing Jobs


The Tez View shows counters so you can understand why a task performs more slowly than expected. Counters help you better understand the task size and enable you to locate anomalies. Elapsed time is one of the primary counters to look for.

Counters are available at the DAG, vertex, and task levels:


**Figure 5.9. Tez View DAG-Level Counters Tab**



**Figure 5.10. Tez View Vertex-Level Counters Tab**



**Figure 5.11. Tez View Task-Level Counters Tab**



### Monitoring Task Progress for Jobs

The Tez View shows task progress by increasing the count of completed tasks and total tasks. This enables you to identify the tasks that might be "hung" and to understand more about long-running tasks.

## 6. Using the Pig View

Apache Pig is a scripting platform for processing and analyzing large data sets. Pig was designed to perform extract-transform-load (ETL) operations, raw data research, and iterative data processing. The **Pig View** provides a web-based interface to compose, edit, and submit Pig scripts, download results, and view logs and the history of job submissions.

This chapter explains:

- [Configuring Your Cluster for the Pig View](#)
- [Creating the Pig View Instance](#)
- [Using the Pig View](#)

### 6.1. Configuring Your Cluster for Pig View

#### Configuring HDFS for Pig

You must set up an HDFS proxy user for the Ambari daemon account. For example, if `ambari-server` daemon is running as `root`, you set up a proxy user for `root` in `core-site` by clicking **HDFS > Configs > Advanced > Custom core-site > Add Property**, and then add the following key-value pairs in the Add Property dialog box:

```
hadoop.proxyuser.root.groups=*
```

```
hadoop.proxyuser.root.hosts=*
```

Click **Add** to add the property to `core-site`.

You must also set up an HDFS proxy user for WebHCat. For example, if your WebHCat server is running as `hcat`, you set up a proxy user for `hcat` in `core-site`. In the same HDFS advanced `core-site` settings pane, click **Add Property**, add the following key-value pairs to the Add Property dialog box, and then click **Add** to add them to `core-site`:

```
hadoop.proxyuser.hcat.groups=*
```

```
hadoop.proxyuser.hcat.hosts=*
```

Ambari views use the `doAs` option for commands. This option enables the Ambari *process user* to impersonate the Ambari *logged-in user*. To avoid receiving permissions errors for job submissions and file save operations, you must create HDFS users for all Ambari users that use the views.

#### Configuring WebHCat for Pig

You must set up a WebHCat proxy user for the Ambari daemon account. For example, if `ambari-server` daemon is running as `root`, you set up a proxy user for `root` in `webhcat-site` by clicking **Hive > Configs > Advanced > Custom webhcat-site > Add Property**, add the following key-value pairs in the Add Property dialog box, and then click **Add** to add them to `webhcat-site`:

```
webhcat.proxyuser.root.groups=*
```

```
webhcat.proxyuser.root.hosts=*
```

## 6.2. Creating the Pig View Instance

1. Browse to the Ambari Administration interface.
2. Click **Views**, expand the **Pig View**, and click **Create Instance**.
3. On the Create Instance page, select **Version**. If multiple Pig View jars are present, choose one.
4. Enter the Details and Settings. The Instance Name appears in the URI, the Display Name appears in the Views drop-down list, and the Description helps multiple users identify the view:

**Figure 6.1. Pig View Details and Settings**

The screenshot shows the configuration page for a Pig View instance. At the top, the 'View' is set to 'PIG' and the 'Version' is '1.0.0'. Below this are two sections: 'Details' and 'Settings'.

**Details:**


- Instance Name: ETL Pig
- Display Name: ETL Pig
- Description: Pig View for ETL team
- Visible:

**Settings:**

- WebHDFS Username: \${username}
- WebHDFS Authentication: auth=SIMPLE
- WebHCat Username: (empty)
- Scripts HDFS Directory\*: /user/\${username}/pig/scripts
- Jobs HDFS Directory\*: /user/\${username}/pig/jobs
- Meta HDFS Directory: /user/\${username}/pig/store

5. Scroll down, and enter the Cluster Configuration information, which tells the Pig View how to access resources in the cluster. For a cluster that is deployed and managed by Ambari, select **Local Ambari Managed Cluster**:

Figure 6.2. Pig View Cluster Configuration



6. Click **Save**, give Permissions to the appropriate users and groups, and click **Go to instance** at the top of the page to go to the view instance.

### 6.2.1. Getting Correct Configuration Values for Manually-Deployed Clusters

If you have manually deployed your cluster, you must enter cluster configuration values in the Pig View Create Instance page. The following table explains where you can find cluster configuration settings in Ambari.

**Table 6.1. Finding Cluster Configuration Values for the Pig View in Ambari**

Property	Value
Scripts HDFS Directory*	/user/\${username}/pig/scripts
Jobs HDFS Directory*	/user/\${username}/pig/jobs
WebHDFS FileSystem URI*	Click <b>HDFS &gt; Configs &gt; Advanced hdfs-site &gt; dfs.namenode.http-address</b> . When you enter the value in the view definition, pre-pend "webhdfs://" to the value you find in the advanced HDFS configuration settings. For example, webhdfs://c6401.ambari.apache.org:50070
WebHCat Hostname*	Click <b>Hive &gt; Configs &gt; Advanced &gt; WebHCat Server &gt; WebHCat Server host</b> to view the hostname. For example, c6402.ambari.apache.org
WebHCat Port*	Click <b>Hive &gt; Configs &gt; Advanced &gt; Advanced webhcat-site &gt; templeton.port</b> to view the port number. For example, 50111

#### For NameNode High Availability


The following values must be entered for primary and secondary NameNodes:

**Table 6.2. Pig View Settings for NameNode High Availability**

Property	Value
First NameNode RPC Address or Second NameNode RPC Address	Select the primary or secondary NameNode to view settings from that host in the cluster. See <a href="#">how to get the NameNode RPC address [19]</a> . When you enter the value in the view definition, pre-pend "http://" to the value you find in the advanced <code>hdfs-site</code> settings. For example, <code>http://c6401.ambari.apache.org:8020</code>
First NameNode HTTP (WebHDFS) Address or Second NameNode HTTP (WebHDFS) Address	Click <b>HDFS &gt; Configs &gt; Advanced &gt; Advanced hdfs-site &gt; dfs.namenode.http-address</b> . When you enter the value in the view definition, pre-pend "http://" to the value you find in the advanced <code>hdfs-site</code> settings. For example, <code>http://c6401.ambari.apache.org:50070</code>

To get First NameNode RPC Address values:

1. Navigate to the HDFS service page in Ambari that contains links to individual NameNodes. Click **NameNode (primary)** or **SNameNode (secondary)** to view the host page:

**Figure 6.3. HDFS Service Page in Ambari**

2. On the host page, click **Configs > Advanced**.
3. Enter "rpc" in the Filter search well at the top right corner of the page or navigate to the **Advanced hdfs-site** settings to find the `dfs.namenode.rpc-address` value that you can enter into the Pig View definition. Here is an example of using the Filter to locate a value:

**Figure 6.4. Using the Filter to Search Advanced hdfs-site Settings**

## 6.2.2. User Permissions for Pig Views

After saving the Pig View instance definition, grant permission on the view for the set of users who can use the view:

**Figure 6.5. Granting User Permissions to Pig Views**

The screenshot shows the Ambari interface for managing a Pig View. At the top, there is a breadcrumb "Views / My Pig View" with a "Go to instance" link and a red "Delete Instance" button. Below this, the view details are shown: "View" is "PIG" and "Version" is "1.0.0".

The "Details" section includes an "Edit" link and the following fields:

- Instance Name: MyPigView
- Display Name: My Pig View
- Description: description
- Visible

The "Permissions" section is highlighted with a red border and contains a table with the following structure:

Permission	Grant permission to these users	Grant permission to these groups
Use	<input type="button" value="Add User"/>	<input type="button" value="Add Group"/>

Below the permissions section is a "Settings" section with an "Edit" link.

### 6.2.3. Kerberos Setup for Pig Views

To set up basic Kerberos for views, see "Set Up Kerberos for Ambari Server" in the [Ambari Security Guide](#). After you have set up basic Kerberos for the Pig View, Pig requires that **WebHDFS Authentication** be set to `auth=KERBEROS;proxyuser=<ambari-user-principal>`

For example, see the following figure:

Figure 6.6. Kerberos Settings for Pig Views

The screenshot shows a 'Properties' dialog box with several fields. The 'WebHDFS Authentication' field is highlighted with a red border and contains the text 'auth=KERBEROS:proxyuser=ambaruser'. Other fields include 'WebHDFS FileSystem URI\*' (webhdfs://erik-views-1.c.pramod-thangai.internal:50070), 'WebHDFS Username' (\$username), 'WebHCat URL\*' (http://erik-views-3.c.pramod-thangai.internal:50111/templeton/v1), 'WebHCat Username' (\$username), 'Dataworker Username' (\$username), 'Scripts HDFS Directory\*' (/user/\${username}/pig/scripts), 'Jobs HDFS Directory\*' (/user/\${username}/pig/jobs), and 'Meta HDFS Directory' (/user/\${username}/pig/store).

## 6.3. Using the Pig View

Use the Pig View to:

- Write Pig scripts
- Execute Pig scripts
- Add user-defined functions (UDFs) to Pig scripts
- View the history of all Pig scripts run by the current user

### 6.3.1. Writing Pig Scripts

Navigate to the Pig View instance Scripts page, and click **New Script** in the upper right corner of the window. Name the script in the New Script dialog box, click **Create**, and enter your script into the editor. After you have written the script, you can use the execute button on the upper right to run it. Check the box that is adjacent to the execute button to use Tez instead of the default MapReduce engine.

The following figure shows a running Pig script:

Figure 6.7. Pig Script Running in the Pig View

The screenshot shows the Pig View interface. The script editor contains the following Pig script:

```

1 batting = load 'batting.csv' using PigStorage(' ');
2 run = FOREACH batting GENERATE $0 as playerId, $1 as year, $2 as runs;
3 grp_data = GROUP run by (year);
4 max_runs = FOREACH grp_data GENERATE group as grp_max(run.run) as max_runs;
5 join_max_run = JOIN max_runs by ($0, max_runs), run by (year,run);
6 join_data = FOREACH join_max_run GENERATE $0 as year, $2 as playerId, $1 as runs;
7 dump join_data;

```

The 'Execute' button is highlighted in blue. Below the script editor, there is an 'Arguments' section with a message: 'This pig script has no arguments defined.' and an 'Add' button.

## 6.3.2. Viewing Pig Script Execution History

The History tab shows the history of Pig scripts run by the current user. A particular script in history can be clicked to open it in a new Script tab to view its details:

Figure 6.8. Pig View Script History Tab



## 6.3.3. User-Defined Functions (UDFs) Tab

UDFs can be added to Pig scripts by clicking **Create UDF** in the upper right corner of the UDFs window. In the Create UDF dialog box, point to a UDF in the system by specifying the name and path:

Figure 6.9. Pig View UDFs Tab



## 7. Using the Capacity Scheduler View

The Yarn Capacity Scheduler allows for multiple tenants in an HDP cluster to share compute resources according to configurable workload management policies.

The Capacity Scheduler View is designed to help hadoop operators configure these policies for YARN. In the View, operators can create hierarchical queues and tune configurations for each queue to define an overall workload management policy for the cluster.

In this section:

- [Configuring your Cluster for the Capacity Scheduler View](#)
- [Creating a Capacity Scheduler View Instance](#)
- [Using the Capacity Scheduler View](#)
- [Troubleshooting](#)

### 7.1. Configuring your Cluster for the Capacity Scheduler View

The Capacity Scheduler View requires that the cluster is managed by Ambari – the view utilizes the Ambari Server API.


### 7.2. Creating a Capacity Scheduler View Instance

When you deploy a cluster using Ambari, a Capacity Scheduler View instance is automatically created. If you do not need to reconfigure the Ambari-created cluster, proceed to the next section, [Using the Capacity Scheduler View](#).


If you have deployed your cluster manually, or if you need to re-configure the Ambari-created Capacity Scheduler View, you can use the information in this section to create and configure a view instance.

Use the following steps to set up a Capacity Scheduler view instance.


1. Select **admin > Manage Ambari** in the Ambari Web top menu.



2. On the Manage Ambari page, click **Views**.



3. On the Views page, click **CAPACITY-SCHEDULER**, then click **Create Instance**.



4. In the Details box on the Create Instance page, type in an instance name, display name, and a description for the view.



### Note

The instance name cannot contain spaces or special characters.

5. In the Cluster Configuration box on the Create Instance page, configure the view to communicate with the HDP cluster.
  - For HDP clusters that are local (managed by the local Ambari Server), select the **Local Ambari Managed Cluster** option, then select the local cluster name.

- To configure the view to work with HDP clusters that are remote (not part of this Ambari Server instance), select the **Custom** option, then specify the remote Ambari cluster API URL and the Ambari cluster user name and password.

6. Click **Save** at the bottom of the page.

The screenshot shows the Ambari interface for creating a new instance of a view. The view selected is 'CAPACITY-SCHEDULER' with version '0.4.0'. The 'Details' section includes fields for 'Instance Name' (Capacity\_Scheduler\_1), 'Display Name' (Capacity Scheduler 1), and 'Description' (Capacity Scheduler configuration 1). A 'Visible' checkbox is checked. The 'Cluster Configuration' section has two options: 'Local Ambari Managed Cluster' (selected) and 'Custom'. Under 'Local Ambari Managed Cluster', the 'Cluster Name' is 'test\_cluster1'. Under 'Custom', the 'Ambari Cluster URL' is 'http://ambari.server:8080/api/v1/clusters/MyCluster', the 'Operator Username' is 'djones', and the 'Operator Password' is masked. A red box highlights the 'Save' button at the bottom right.

7. The Capacity Scheduler View instance is created, and the configuration page for the instance appears.

The screenshot displays the Ambari web interface for configuring a Capacity Scheduler view instance. The interface is organized into several sections:

- Navigation Menu (Left):** Includes 'Clusters' (with 'test\_cluster1' selected), 'Views', and 'User + Group Management' (with 'Users' and 'Groups' sub-items).
- Header:** Shows 'Ambari' logo, a user profile for 'admin', and a 'Delete Instance' button.
- View Information:** Displays 'Views / Capacity Scheduler 1' with a 'Go to Instance' link and a 'Delete Instance' button.
- View Details:** Shows the view name 'CAPACITY-SCHEDULER' and version '0.4.0'.
- Details Section:** Contains fields for 'Instance Name' (Capacity\_Scheduler\_1), 'Display Name' (Capacity Scheduler 1), and 'Description' (Capacity Scheduler configuration 1). A 'Visible' checkbox is checked.
- Permissions Section:** Features a table with columns for 'Permission', 'Grant permission to these users', and 'Grant permission to these groups'. A 'Use' row includes 'Add User' and 'Add Group' buttons.
- Cluster Configuration Section:** Offers two options: 'Local Ambari Managed Cluster' (selected) with a 'Cluster Name' dropdown set to 'test\_cluster1', and 'Custom' with fields for 'Ambari Cluster URL\*' (http://ambari.server:8080/api/v1/clusters/MyCluster), 'Operator Username\*' (admin), and 'Operator Password\*'.

## 7.2.1. User Permissions for Capacity Scheduler Views

Use the following procedure to add users and groups to a Capacity Scheduler view instance.

1. On the Capacity Scheduler view instance configuration page, click the box labeled Add User in the Permissions box.

The screenshot displays the Ambari web interface for configuring a Capacity Scheduler instance. The left sidebar shows navigation options for Clusters, Views, and User + Group Management. The main content area is titled "Views / Capacity Scheduler 1" and includes a "Delete Instance" button. The "View" is identified as "CAPACITY-SCHEDULER" with a version of "0.4.0".

The "Details" section contains the following information:

- Instance Name: Capacity\_Scheduler\_1
- Display Name: Capacity Scheduler 1
- Description: Capacity Scheduler configuration 1
- Visible:

The "Permissions" section is divided into two columns: "Grant permission to these users" and "Grant permission to these groups". Under the "Grant permission to these users" column, there is a "Use" label and an "Add User" button, which is highlighted with a red rectangle. The "Grant permission to these groups" column has an "Add Group" button.


The "Cluster Configuration" section shows two options:

- Local Ambari Managed Cluster: Selected, with Cluster Name set to "test\_cluster1".
- Custom: Unselected, with Ambari Cluster URL\* set to "http://ambari.server:8080/api/v1/clusters/MyCluster".

2. Enter user names in the Use box, then click the blue check mark to add the users. You can use the same method to add groups in the Add Group box.

The screenshot displays the Ambari web interface for configuring a Capacity Scheduler instance. The left sidebar shows navigation options for Clusters, Views, and User + Group Management. The main content area is titled 'Views / Capacity Scheduler 1' and includes a 'Delete Instance' button. The 'View' is identified as 'CAPACITY-SCHEDULER' with version '0.4.0'. The 'Details' section contains input fields for 'Instance Name', 'Display Name', and 'Description', along with a 'Visible' checkbox. The 'Permissions' section features a table with columns for 'Permission', 'Grant permission to these users', and 'Grant permission to these groups'. The 'Grant permission to these users' field is highlighted with a red box and contains the text 'barnh x djones x'. The 'Cluster Configuration' section shows the 'Local Ambari Managed Cluster' option selected, with 'Cluster Name' set to 'test\_cluster1' and 'Ambari Cluster URL' set to 'http://ambari.server:8080/api/v1/clusters/MyCluster'.

3. After you have finished adding users and groups, click **Go to instance** at the top of the page to open the Capacity Scheduler view instance.



4. The Capacity Scheduler view instance page appears.

The screenshot displays the Ambari interface for configuring the Capacity Scheduler. At the top, there are navigation tabs for Dashboard, Services, Hosts, Alerts, and Admin. The main content area is divided into several sections:

- Queues:** A list of queues with their status. 'root (100%)' and 'default (100%)' are shown with green progress bars and checkmarks.
- Scheduler:** A configuration section with the following parameters:
  - Maximum Applications: 10000
  - Maximum AM Resource: 20%
  - Node Locality Delay: -40
  - Calculator: org.apache.hadoop.yarn
- Versions:** A section showing the current version 'v1 Current' and a 'load' button.

## 7.3. Using the Capacity Scheduler View

The Capacity Scheduler View is designed to help hadoop operators configure workload management policies for YARN. In the Capacity Scheduler View, operators can create hierarchical queues and tune configurations for each queue to define an overall workload management policy for the cluster.

### 7.3.1. Setting up Queues


Use the following steps to set up Capacity Scheduler queues on a view instance.

1. On the Capacity Scheduler view instance configuration page, click **Add Queue**. The queue will be added under the top level, or "root" queue. A "default" queue already exists under the root queue.




#### Note

To return to a previously created Capacity Scheduler view instance, click **Views** on the Manage Ambari page, then click **CAPACITY-SCHEDULER**. Click the applicable Capacity Scheduler view instance, then click **Go to instance** at the top of the page.



- 2. Type in a name for the new queue, then click the green check mark to create the queue. In the following example, we're creating the "Engineering" queue.



- 3. The "Engineering" queue is added, and its configuration page appears.

The screenshot shows the Ambari Capacity Scheduler configuration for the 'Engineering' queue. On the left, a list of queues shows 'root (100%)', 'default (100%)', and 'Engineering (0%)'. The 'Engineering' queue is selected. The 'Capacity' section shows 'Level Total' at 100%. The 'Engineering' queue's capacity is set to 0%, and its maximum capacity is also 0%. The 'Access Control and Status' section shows the state as 'Running'. The 'Resources' section shows various limits like 'User Limit Factor' at 1 and 'Minimum User Limit' at 100%.


4. The sum of queue capacities at any level in the Capacity Scheduler configuration must total 100%. Here the default queue is already set to 100%. Therefore, if we try to set the "Engineering" queue capacity to 60%, error messages appear warning that the total at this level is 160%.

The screenshot shows the Ambari Capacity Scheduler configuration for the 'Engineering' queue. On the left, the 'default' queue is highlighted in red, indicating an error. The 'Level Total' bar at the top right shows 160%. The 'Engineering' queue's capacity is set to 60%, and its maximum capacity is also 60%. The 'Access Control and Status' section shows the state as 'Running'. The 'Resources' section shows various limits like 'User Limit Factor' at 1 and 'Minimum User Limit' at 100%.


5. If we click the "default" queue and set its capacity to 0%, the error messages no longer appear, and the Level Total bar at the top of the page lists the total queue capacity at this level as 60%.

6. To add more queues at the root level, click the **root** queue, then click **Add Queue**. In the following example, we have added a "Support" queue set to 10% of the level capacity, and a "Marketing" queue set to 30%. The root-level queue capacities now total 100%.

7. To save your configuration, click **Actions > Save Only**. On the **Notes** pop-up, enter an optional description of your changes, then click **Save**. Each version is retained and listed in the Versions box.



8. To build a queue hierarchy, click a top level queue, then click Add Queue. In the following example, the "qa" and "development" queues have been added under the "Engineering" queue.



## 7.3.2. Configuring Queues

To configure a queue, click the queue name, then set the following queue parameters:



### Note

Hold the cursor over a parameter name to display a description of the parameter.

### Capacity

- Capacity – The percentage of cluster resources available to the queue. For a sub-queue, the percentage of parent queue resources.
- Max Capacity – The maximum percentage of cluster resources available to the queue. Setting this value tends to restrict elasticity, as the queue will be unable to utilize idle cluster resources beyond this setting.
- Enable Node Labels – Select this check box to enable node labels for the queue.


### Access Control and Status

- State – Running is the default state. Setting this to Stopped lets you gracefully drain the queue of jobs (for example, before deleting a queue).
- Administer Queue – Click **Custom** to restrict administration of the queue to specific users and groups.
- Submit Applications – Click **Custom** to restrict the ability to run applications in the queue to specific users and groups.

### Resources


- User Limit Factor – The default value of "1" means that any single user in the queue can at maximum only occupy the queue's configured capacity. This prevents users in a single queue from monopolizing resources across all queues in a cluster. Setting the value to "2" would restrict the queue's users to twice the queue's configured capacity. Setting it to a value of 0.5 would restrict any user from using resources beyond half of the queue capacity.
- Minimum User Limit – This property can be used to set the minimum percentage of resources allocated to each queue user. For example, to enable equal sharing of the queue capacity among five users, you would set this property to 20%.
- Maximum Applications – This setting enables you to override the Scheduler Maximum Applications setting (described in [Configuring Cluster Scheduler Settings](#)). The default setting is Inherited (no override).
- Maximum AM Resource – This setting enables you to override the Scheduler Maximum AM Resource setting (described in [Configuring Cluster Scheduler Settings](#)). The default setting is Inherited (no override).
- Ordering Policy – You can specify FIFO (First In, First Out) or fair (Fair Scheduler: applications get a fair share of capacity regardless of the order in which they were submitted).

The following image shows the example "Engineering" queue with these settings specified:



### 7.3.3. Configuring Cluster Scheduler Settings

You can use the Scheduler box to set global capacity scheduler settings that apply to all queues.



The following Scheduler global parameters are available:

- **Maximum Applications** – To avoid system-thrash due to an unmanageable load – caused either by malicious users, or accidentally – the Capacity Scheduler enables you to place a static, configurable limit on the total number of concurrently active (both running and pending) applications at any one time. This property is used to set this limit, with a default value of 10,000.
- **Maximum AM Resource** – The limit for running applications in any specific queue is a fraction of this total limit, proportional to its capacity. This is a hard limit, which means that once this limit is reached for a queue, any new applications submitted to that queue will be rejected, and clients will have to wait and retry later.
- **Node Locality Delay** – The number of missed scheduling cycles after which the scheduler attempts to schedule rack-local containers.
- **Calculator** – The method by which the scheduler calculates resource capacity across resource types.

### 7.3.4. Applying the Configuration Changes


You can use the Actions menu to apply configuration changes made to the queue hierarchy.

Depending on the configuration changes made, the Actions menu will guide you to the options available to apply the changes.


For changes that are not valid and cannot be applied, the **Actions** button will turn red, and the menu will not appear.

The screenshot displays a user interface for managing YARN queues. At the top, there are two buttons: a white button with a plus sign and the text '+ Add Queue', and a red button with a refresh icon and the text 'Actions'. Below these buttons is a list of queue entries. The first entry is 'root (100%)' with a green progress bar and a green checkmark. The second entry is 'default (62%)' with a red progress bar, a red warning triangle icon, and a blue pencil icon. The third entry is 'Scheduler' with a grey background and a green checkmark.

For configuration changes that can be applied dynamically (without restarting the YARN ResourceManager), the Actions Menu will guide you to **Save and Refresh Queues**.




For configuration changes that require a restart of the YARN ResourceManager, the Actions Menu will guide you to **Save and Restart ResourceManager**.



## 7.4. Troubleshooting

If you encounter an issue where the configurations cannot be applied from the View, you should go to the local Ambari Server instance managing the cluster and directly edit the Capacity Scheduler configuration from the YARN configuration page.

In the local Ambari instance, navigate to **Services > YARN**, then select the **Configs** tab. On the **Advanced** tab, expand the Scheduler section.



▼ Scheduler

yarn.resourcemanager.scheduler.class `org.apache.hadoop.yarn.server.resourcemanager.scheduler.capacity.CapacityScheduler` 🔒 + ↻

Capacity Scheduler

```
yarn.scheduler.capacity.maximum-am-resource-percent=0.2
yarn.scheduler.capacity.maximum-applications=10000
yarn.scheduler.capacity.node-locality-delay=40
yarn.scheduler.capacity.queue-mappings-override.enable=false
yarn.scheduler.capacity.root.accessible-node-labels=*
yarn.scheduler.capacity.root.acl_administer_queue=*
yarn.scheduler.capacity.root.capacity=100
yarn.scheduler.capacity.root.default.acl_submit_applications=*
yarn.scheduler.capacity.root.default.capacity=100
yarn.scheduler.capacity.root.default.maximum-capacity=100
```

+ ↻

Here you will be able to edit the underlying configurations for the Capacity Scheduler and fix any issues you may encounter.

## 8. Using the Hive View

Hive is a data warehouse infrastructure built on top of Hadoop. It provides tools to enable data ETL, a mechanism to put structures on the data, and the capability to query and analyze large data sets that are stored in Hadoop. The **Hive View** is designed to help you author, execute, understand, and debug Hive queries.

This chapter explains:

- [Configuring Your Cluster](#)
- [Creating the Hive View Instance](#)
- [Using the Hive View](#)
- [Troubleshooting](#)



### Important

The Tez View integrates with the Hive View. Please install the Tez View when you install the Hive View. See [Using the Tez View](#) for more information.



### Important

It is critical that you prepare your Ambari Server for hosting views. It is strongly recommended you increase the amount of memory available to your Ambari Server, and that you run additional “standalone” Ambari Servers to host the views. See [Preparing Ambari Server for Views](#) and [Running Ambari Server Standalone](#) for more information.

## 8.1. Configuring Your Cluster

For the Hive View to access HDFS, the Ambari Server daemon hosting the view needs to act as the proxy user for HDFS. This allows Ambari to submit requests to HDFS on behalf of the users using the Hive View. This is critical since the Hive View will store metadata about their user Hive queries in HDFS. This also means users that will access the Hive View must have a user directory setup in HDFS.

- [Setup HDFS Proxy User](#)
- [Setup HDFS User Directory](#)

### 8.1.1. Setup HDFS Proxy User

To set up an HDFS proxy user for the Ambari Server daemon account, you need to configure the proxy user in the HDFS configuration. This configuration is determined by the account name the **ambari-server** daemon is running as. For example, if your **ambari-server** is running as **root**, you set up an HDFS proxy user for **root** with the following:

1. In Ambari Web, browse to **Services > HDFS > Configs**.

2. Under the **Advanced** tab, navigate to the **Custom core-site** section.
3. Click **Add Property...** to add the following custom properties:

```
hadoop.proxyuser.root.groups=*
hadoop.proxyuser.root.hosts=*
```

Notice the **ambari-server** daemon account name `root` is part of the property name. Be sure to modify this property name for the account name you are running the `ambari-server` as. For example, if you were running `ambari-server` daemon under an account name of `ambariusr`, you would use the following properties instead:

```
hadoop.proxyuser.ambariusr.groups=*
hadoop.proxyuser.ambariusr.hosts=*
```

Similarly, if you have configured [Ambari Server for Kerberos](#), be sure to modify this property name for the **primary Kerberos principal** user. For example, if `ambari-server` is setup for Kerberos using principal `ambari-server@EXAMPLE.COM`, you would use the following properties instead:

```
hadoop.proxyuser.ambari-server.groups=*
hadoop.proxyuser.ambari-server.hosts=*
```

4. Save the configuration change and restart the required components as indicated by Ambari.

## 8.1.2. Setup HDFS User Directory

The Hive View stores user metadata in HDFS. By default, the location in HDFS for this metadata is `/user/${username}` where `${username}` is the username of the currently logged in user that is accessing the Hive View.



### Important

Since many users leverage the default Ambari admin user for getting started with Ambari, the `/user/admin` folder needs to be created in HDFS. Therefore, be sure to create the admin user directory in HDFS using these instructions prior to using the view.

To create user directories in HDFS, do the following for each user you plan to have use the Hive View.

1. Connect to a host in the cluster that includes the HDFS client.
2. Switch to the `hdfs` system account user.

```
su - hdfs
```

3. Using the HDFS client, make an HDFS directory for the user. For example, if your username is `admin`, you would create the following directory.

```
hadoop fs -mkdir /user/admin
```

4. Set the ownership on the newly created directory. For example, if your username is `admin`, you would make that user the directory owner.

```
hadoop fs -chown admin:hadoop /user/admin
```

## 8.2. Creating the Hive View Instance

1. Browse to the Ambari Administration interface.
2. Click **Views**, expand the **Hive View**, and click **Create Instance**.
3. On the Create Instance page, select the **Version**. If multiple Hive View jars are present, choose one.
4. Enter the following view instance Details:

**Table 8.1. Hive View Instance Details**

Property	Description	Example Value
Instance Name	This is the Hive view instance name. This value should be unique for all Hive view instances you create. This value cannot contain spaces and is required.	HIVE_1
Display Name	This is the name of the view link displayed to the user in Ambari Web.	Hive
Description	This is the description of the view displayed to the user in Ambari Web.	Author and execute Hive queries.
Visible	This checkbox determines whether the view is displayed to users in Ambari Web.	Visible or Not Visible

5. The **Settings** and **Cluster Configuration** options depend on a few cluster and deployment factors in your environment. You can typically leave the default **Settings** unless you are using the Hive View with a Kerberos enabled cluster. Refer to [Settings and Cluster Configuration](#) for more information.
6. Click **Save**.

### 8.2.1. Settings and Cluster Configuration

If you have manually deployed your cluster, you must enter cluster configuration values in the Hive View Create Instance page. The following table explains where you can find cluster configuration settings in Ambari.

**Table 8.2. Finding Cluster Configuration Values for the Hive View in Ambari**

Property	Value
Hive Authentication	auth=NONE;user=\${username}
Scripts HDFS Directory*	/user/\${username}/hive/scripts
Jobs HDFS Directory*	/user/\${username}/hive/jobs
HiveServer2 Host*	Click <b>Hive &gt; Summary &gt; HiveServer2</b> to view the host name. For example, c6401.ambari.apache.org
HiveServer2 Thrift port*	Click <b>Hive &gt; Configs &gt; Advanced &gt; General &gt; HiveServer2 Port</b> . For example, 10000

Property	Value
WebHDFS FileSystem URI*	Click <b>HDFS &gt; Configs &gt; Advanced &gt; Advanced hdfs-site &gt; dfs.namenode.http-address</b> . When you enter the value in the view definition, pre-pend "webhdfs://" to the value you find in the advanced HDFS configuration settings. For example, webhdfs://c6401.ambari.apache.org:50070
YARN Application Timeline Server URL*	Click <b>YARN &gt; Configs &gt; Advanced &gt; Application Timeline Server &gt; yarn.timeline-service.webapp.address</b> . When you enter the value in the view definition, pre-pend "http://" to the value you find in the YARN advanced configuration settings. For example, http://c6401.ambari.apache.org:8188
YARN ResourceManager URL*	Click <b>YARN &gt; Configs &gt; Advanced &gt; Advanced yarn-site &gt; yarn.resourcemanager.webapp.address</b> . When you enter the value in the view definition, pre-pend "http://" to the value you find in the YARN advanced configuration settings. For example, http://c6401.ambari.apache.org:8088

### For NameNode High Availability

The following values must be entered for primary and secondary NameNodes:


**Table 8.3. Hive View Settings for NameNode High Availability**

Property	Value
First NameNode RPC Address or Second NameNode RPC Address	Select the primary or secondary NameNode to view settings from that host in the cluster. See <a href="#">how to get the NameNode RPC address [43]</a> . When you enter the value in the view definition, pre-pend "http://" to the value you find in the advanced hdfs-site settings. For example, http://c6401.ambari.apache.org:8020
First NameNode HTTP (WebHDFS) Address or Second NameNode HTTP (WebHDFS) Address	Click <b>HDFS &gt; Configs &gt; Advanced &gt; Advanced hdfs-site &gt; dfs.namenode.http-address</b> . When you enter the value in the view definition, pre-pend "http://" to the value you find in the advanced hdfs-site settings. For example, http://c6401.ambari.apache.org:50070

To get First NameNode RPC Address values:

1. Navigate to the HDFS service page in Ambari that contains links to individual NameNodes. Click **NameNode (primary)** or **SNameNode (secondary)** to view the host page:


**Figure 8.1. HDFS Service Page in Ambari**



2. On the host page, click **Configs > Advanced**.
3. Enter "rpc" in the Filter search well at the top right corner of the page or navigate to the **Advanced hdfs-site** settings to find the `dfs.namenode.rpc-address` value that you

can enter into the Hive View definition. Here is an example of using the Filter to locate a value:


**Figure 8.2. Using the Filter to Search Advanced hdfs-site Settings**



### 8.2.2. User Permissions for Hive Views

After saving the Hive View instance definition, grant permission on the view for the set of users who can use the view:

**Figure 8.3. Granting User Permissions to Hive Views**



### 8.2.3. Kerberos Setup for Hive Views

To set up basic Kerberos for views, see "Set Up Kerberos for Ambari Server" in the [Ambari Security Guide](#). After you have set up basic Kerberos for the Hive View, Hive requires the following additional settings:

**Table 8.4. Kerberos Settings for Hive Views**

Property	Value
<b>WebHDFS Authentication</b>	auth=KERBEROS;proxyuser=<ambari-principal>
<b>Hive Authentication</b>	KERBEROS and the principal is set to the same principal that is specified in hive-site.xml for hive.server2.authentication.kerberos.principal. For example, see the following figure.

**Figure 8.4. Hive View Kerberos Configuration Example**

The screenshot displays two configuration panels. The top panel, titled 'Settings', includes fields for 'Hive Authentication' (set to 'auth=KERBEROS:principal-hive/erik-bb2-2.c.pramod-thangali.internal@EXAMPLE.COM'), 'WebHDFS Username' (set to '\$(username)'), 'WebHDFS Authentication' (set to 'auth=KERBEROS:proxyuser-ambariuser'), 'Instance name of Tez view' (set to 'TEZ\_CLUSTER\_INSTANCE'), 'Scripts HDFS Directory\*' (set to 'User/\$(username)/hive/scripts'), 'Jobs HDFS Directory\*' (set to 'User/\$(username)/hive/jobs'), and 'Default script settings file\*' (set to 'User/\$(username)/\$(instanceName).defaultSettings'). The bottom panel, titled 'Cluster Configuration', shows 'Local Ambari Managed Cluster' with 'Cluster Name' set to 'views', and 'Custom' settings where 'HiveServer2 Host\*' is set to 'erik-bb2-2.c.pramod-thangali.internal'. Other fields include 'HiveServer2 Thrift port\*' (10000), 'WebHDFS FileSystem URI\*' (webhdfs://erik-bb2-1.c.pramod-thangali.internal:50070), and YARN Application Timeline Server and Resource Manager URLs.

## 8.3. Using the Hive View

Use the Hive View to:

- Browse databases
- Write and execute queries
- Manage query execution jobs and history


### 8.3.1. Query Tab

Click the **Query** tab to browse database tables and columns and to build, execute, and debug queries.

#### Database Explorer

The Database Explorer enables you to view all databases and tables in Hive that you have permissions to view. It is designed to navigate a large number of databases, tables, and columns:

Figure 8.5. Hive View Database Explorer




#### Features of Database Explorer:

- Click the refresh icon in the top right to view tables that were created since the Hive View session began.
- Select a database from the drop-down list. All queries in the current tab are then run against the selected database. You can also edit the drop-down list to enable substring searches over a large number of databases.
- Use the Search tables and Search columns fields to search when you have a large number of tables and columns.
- Browse the Databases tab to view all of the databases, tables, and columns. This is useful when you are authoring queries. The icon to the right of a table enables you to see sample data within that table.

#### Query Editor

You can author and execute queries in the Query Editor:


Figure 8.6. Query Editor



#### Features and Behavior of Query Editor

- All queries contained in a Worksheet tab execute sequentially, and they run in the same session. Running all queries in one pass requires handling the output of multiple select statements and is not supported in the 1.0 version.
- To run a specific query, highlight it, and click **Execute**.
- When the first query is executed in a Worksheet, a Tez session is opened.
- Click **Save as** to save your query.
- Double-click the **Worksheet** tab to rename the query, click **OK**, and then **Save as** to save the query with the new name.
- Click **New Worksheet** to open a new worksheet tab. Queries executed from the new worksheet tab will execute in a different session. Queries from different worksheets can execute in parallel.
- Press **CTRL + space** to autocomplete query statements.
- Click the double arrow icon in the upper right corner of the Query Editor to expand the Worksheet area and cover Database Explorer. Click the icon again to collapse the Worksheet and make Database Explorer available again.
- Click the icon at the bottom of the Worksheet window and drag it down to expand the authoring space.
- Query results and logs display below the query when it is executed.

**Figure 8.7. Query Results and Logs in Hive View Query Editor**



### Query Editor Settings

Click the gear icon on the right margin of the worksheet to access settings for the Query Editor. Then click **Add**, select a setting parameter from the drop-down list, and then select a value for the parameter. Query Editor settings are configured per worksheet.

To save settings as default settings so they are applied each time that a new worksheet is opened, click **Save Default Settings** in the upper right corner of the settings window.


Click **SQL** to the right of the Worksheet window to exit settings and return to the Query Editor authoring pane.

### Text Explain and Visual Explain

There are two options that help you understand how your queries are executed. One is a textual explanation of your query and the other form explains the query visually as a diagram. In future releases, column lineage will be added.


The **Explain** button in the lower left corner of the Worksheet window launches a textual explanation:

**Figure 8.8. Query Editor Textual Explain Feature**



To launch the Visual Explain diagram, click the link icon to the right of the Worksheet window. If the query is running, Visual Explain shows the query execution progress per vertex:


**Figure 8.9. Query Editor Visual Explain Feature**



### Using the Tez View to Debug Query Execution

Query execution can be debugged using the embedded Tez view. To access the Tez view, click **TEZ** in the toolbar on the right of the Worksheet window:

Figure 8.10. Tez View Query Debugging Option




When a query fails, the Status field displays **FAILED** and there is a link to Failed Tasks and the error displays on the first page. Click **Download data** to get the data for the task. For further details on debugging, see the Tez View.

### Errors and Alerts


Errors and alerts can be viewed by clicking the envelope icon in the toolbar to the right of the Worksheet window. When the icon is clicked, all the messages are shown with a one-line summary per message:

Figure 8.11. Query Editor Error Message Summary Window



If you want to view details of the errors, expand the summary by clicking it. The details text can be copied into a bug report:


Figure 8.12. Query Editor Error Message Details Window



## 8.3.2. Saved Queries Tab

The Saved Queries tab shows all the queries that have been saved by the current user. Click the gear icon to the right of the query list to view the history of a query or to delete it:


Figure 8.13. Saved Queries Tab



### 8.3.3. History Tab

You can view the history of all jobs run by the current user in the History tab. It pulls history from the Application Timeline Server database. All queries for which logs are present in that database are displayed here. This means that regardless of the source of the query, (CLI, JDBC/ODBC, Hive View) it will appear here on the History tab. Queries that have not been assigned a name, such as those created in the Hive View, appear as query text. For example, see the insert statement that was submitted by CLI in the following image:

Figure 8.14. History Tab




For queries that are submitted from the Hive View, a Stop Execution button is available to enable you to end a currently running query. When you select a query by clicking the title in the first column, that query appears on a new sub-tab in the Query tab where it can be analyzed and debugged.

### 8.3.4. UDF Tab

User-defined functions (UDFs) can be added to queries by pointing to a JAR file on HDFS, which contains the UDF definition. After the UDF is added here, an Insert UDF button appears in the Query Editor that enables you to add the UDF to your query:

Figure 8.15. UDF Tab



## 8.4. Troubleshooting

**Table 8.5. Troubleshooting Hive Views Errors**

Error	Solution
User: root is not allowed to impersonate admin	HDFS has not been configured for Ambari as a proxy user. Refer to <a href="#">Setup HDFS Proxy User</a> .
E090 HDFS020 Could not write file /user/admin/hive/jobs/hive-job-1-2015-10-30_02-12/query.hql [HdfsApiException]	The user does not have a user directory in HDFS for the view to store metadata about the view. Refer to <a href="#">Setup HDFS User Directory</a> .

## 9. Using the Slider View

Slider is a framework for deploying and managing long-running applications on YARN. When applications are packaged using Slider for YARN, the **Slider View** can be used to help deploy and manage those applications from Ambari.

### 9.1. Deploying the Slider View

Refer to the Ambari Administration guide for general information about [Managing Views](#).

1. From the Ambari Administration interface, browse to the Views section.
2. Click to expand the **Slider** view and click **Create Instance**.
3. Enter the instance name, the display name and description.
4. Enter the configuration properties for your cluster.

Property	Description	Example
Ambari Server URL (required)	The Ambari REST URL to the cluster resource.	http://ambari.server:8080/api/v1/clusters/MyCluster
Ambari Server Username (required)	The username to connect to Ambari. Must be an Ambari Admin user.	admin
Ambari Server Password (required)	The password for the Ambari user.	password
Slider User	The user to deploy slider applications as. By default, the applications will be deployed as the "yarn" service account user. To use the current logged-in Ambari user, enter <code>\${username}</code> .	joe.user or <code>\${username}</code>
Kerberos Principal	The Kerberos principal for Ambari views. This principal identifies the process in which the view runs. Only required if your cluster is configured for Kerberos. Be sure to configure the view principal as a proxy user in core-site.	view-principal@EXAMPLE.CO
Kerberos Keytab	The Kerberos keytab for Ambari views. Only required if your cluster is configured for Kerberos.	/path/to/keytab/view-principal.headless.keytab

5. Save the view.

## 10. Using the Files View

The **Files View** provides a convenient way to access HDFS through a web-based interface. This document provides information on how to configure a view instance and your cluster for browsing HDFS via the **Files View**.

- [Configuring Your Cluster](#)
- [Creating and Configuring a Files View Instance](#)
- [Troubleshooting](#)



### Important

It is critical that you prepare your Ambari Server for hosting views. It is strongly recommended you increase the amount of memory available to your Ambari Server, and that you run additional “standalone” Ambari Servers to host the views. See [Preparing Ambari Server for Views](#) and [Running Ambari Server Standalone](#) for more information.

### 10.1. Configuring Your Cluster for Files View

#### Configuring HDFS for Files View

You need to set up an HDFS proxy user for the Ambari daemon account. For example, if `ambari-server` daemon is running as `root`, you set up a proxy user for `root` in `core-site` by adding and changing properties in `HDFS > Configs > Custom core-site`:

```
hadoop.proxyuser.root.groups=*
```

```
hadoop.proxyuser.root.hosts=*
```

Restart the required components as indicated by Ambari. If you want to add multiple views, you can restart services once, after making changes for all views.

### 10.2. Creating the Files View Instance

1. Browse to the Ambari Administration interface.
2. Click Views, expand the **Files View**, and click **Create Instance**.
3. Enter the following information:

Property	Value
Instance Name	FILES_1
Display Name	MyFiles
Description	Browse HDFS files and directories.
WebHDFS FileSystem URI	webhdfs://<HDFS > configs > Advanced hdfs-site > dfs.namenode.http-address> For example: webhdfs://c6401.ambari.apache.org:50070
WebHDFS Username	\${username}

4. Click **Save**, give Permissions to the appropriate users and groups, and go to the view instance.