

Managing Alert Policies using Streams Messaging Manager

Date published: 2019-09-20

Date modified: 2022-08-30



Legal Notice

© Cloudera Inc. 2024. All rights reserved.

The documentation is and contains Cloudera proprietary information protected by copyright and other intellectual property rights. No license under copyright or any other intellectual property right is granted herein.

Unless otherwise noted, scripts and sample code are licensed under the Apache License, Version 2.0.

Copyright information for Cloudera software may be found within the documentation accompanying each component in a particular release.

Cloudera software includes software from various open source or other third party projects, and may be released under the Apache Software License 2.0 (“ASLv2”), the Affero General Public License version 3 (AGPLv3), or other license terms. Other software included may be released under the terms of alternative open source licenses. Please review the license and notice files accompanying the software for additional licensing information.

Please visit the Cloudera software product page for more information on Cloudera software. For more information on Cloudera support services, please visit either the Support or Sales page. Feel free to contact us directly to discuss your specific needs.

Cloudera reserves the right to change any products at any time, and without notice. Cloudera assumes no responsibility nor liability arising from the use of products, except as expressly agreed to in writing by Cloudera.

Cloudera, Cloudera Altus, HUE, Impala, Cloudera Impala, and other Cloudera marks are registered or unregistered trademarks in the United States and other countries. All other trademarks are the property of their respective owners.

Disclaimer: EXCEPT AS EXPRESSLY PROVIDED IN A WRITTEN AGREEMENT WITH CLOUDERA, CLOUDERA DOES NOT MAKE NOR GIVE ANY REPRESENTATION, WARRANTY, NOR COVENANT OF ANY KIND, WHETHER EXPRESS OR IMPLIED, IN CONNECTION WITH CLOUDERA TECHNOLOGY OR RELATED SUPPORT PROVIDED IN CONNECTION THEREWITH. CLOUDERA DOES NOT WARRANT THAT CLOUDERA PRODUCTS NOR SOFTWARE WILL OPERATE UNINTERRUPTED NOR THAT IT WILL BE FREE FROM DEFECTS NOR ERRORS, THAT IT WILL PROTECT YOUR DATA FROM LOSS, CORRUPTION NOR UNAVAILABILITY, NOR THAT IT WILL MEET ALL OF CUSTOMER’S BUSINESS REQUIREMENTS. WITHOUT LIMITING THE FOREGOING, AND TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, CLOUDERA EXPRESSLY DISCLAIMS ANY AND ALL IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, QUALITY, NON-INFRINGEMENT, TITLE, AND FITNESS FOR A PARTICULAR PURPOSE AND ANY REPRESENTATION, WARRANTY, OR COVENANT BASED ON COURSE OF DEALING OR USAGE IN TRADE.

Contents

- Introduction to alert policies in Streams Messaging Manager..... 4**
- Component types and metrics for alert policies.....4**
- Notifiers.....8**
- Managing alert policies and notifiers in SMM.....8**
 - Creating a notifier.....8
 - Updating a notifier.....9
 - Deleting a notifier..... 10
 - Creating an alert policy..... 10
 - Updating an alert policy..... 11
 - Enabling an alert policy..... 12
 - Disabling an alert policy..... 12
 - Deleting an alert policy..... 12

Introduction to alert policies in Streams Messaging Manager

You can configure an alert policy in Streams Messaging Manager (SMM). When an alert policy triggers, SMM creates an alert. You can modify alert policy names, descriptions, and can enable or disable alert policies. You can also delete alert policies.

An alert policy sends notifications through a notifier based on the conditions that you configure in the alert policy.

An alert consists of details of the policy including the alert message and the conditions that fire the alert. You can use these alerts to monitor the health of different Kafka entity types, latency, and Kafka cluster replications in your system, and to identify and troubleshoot problems.

When you navigate to the Alerts window, the Alerts Overview page appears as shown in the following image:

Title	Timestamp	Component name	Type	State	Payload
Alert: Replication Flow D...	1d 12h 32m 47s ago	ANY	CLUSTER_REPLICATION	CLEARED	Alert policy: "ALERT IF (CLUSTER_REPLICATION (cluster="CDFCluster") ... show more
Alert: Replication Flow D...	1d 12h 37m 48s ago	ANY	CLUSTER_REPLICATION	RAISED	Alert policy: "ALERT IF (CLUSTER_REPLICATION (cluster="CDFCluster") ... show more
Alert: Replication Flow D...	1d 12h 42m 49s ago	ANY	CLUSTER_REPLICATION	RAISED	Alert policy: "ALERT IF (CLUSTER_REPLICATION (cluster="CDFCluster") ... show more
Alert: Replication Flow D...	1d 12h 47m 49s ago	ANY	CLUSTER_REPLICATION	RAISED	Alert policy: "ALERT IF (CLUSTER_REPLICATION (cluster="CDFCluster") ... show more
Alert: Replication Flow D...	1d 12h 52m 50s ago	ANY	CLUSTER_REPLICATION	RAISED	Alert policy: "ALERT IF (CLUSTER_REPLICATION (cluster="CDFCluster") ... show more
Alert: Replication Flow D...	1d 12h 57m 51s ago	ANY	CLUSTER_REPLICATION	RAISED	Alert policy: "ALERT IF (CLUSTER_REPLICATION (cluster="CDFCluster") ... show more
Alert: Replication Flow D...	1d 13h 2m 52s ago	ANY	CLUSTER_REPLICATION	RAISED	Alert policy: "ALERT IF (CLUSTER_REPLICATION (cluster="CDFCluster") ... show more
Alert: Replication Flow D...	1d 13h 7m 53s ago	ANY	CLUSTER_REPLICATION	RAISED	Alert policy: "ALERT IF (CLUSTER_REPLICATION (cluster="CDFCluster") ... show more
Alert: Replication Flow D...	1d 13h 12m 54s ago	ANY	CLUSTER_REPLICATION	RAISED	Alert policy: "ALERT IF (CLUSTER_REPLICATION (cluster="CDFCluster") ... show more
Alert: Replication Flow D...	1d 13h 17m 54s ago	ANY	CLUSTER_REPLICATION	RAISED	Alert policy: "ALERT IF (CLUSTER_REPLICATION (cluster="CDFCluster") ... show more
Alert: Replication Flow D...	1d 13h 22m 55s ago	ANY	CLUSTER_REPLICATION	RAISED	Alert policy: "ALERT IF (CLUSTER_REPLICATION (cluster="CDFCluster") ... show more

You can check the list of alerts that occurred in the system till date on the HISTORY page. You can check the title, timestamp details, component name, type, state, and payload information of an alert. You can click show more to check complete payload details for an alert. Click ACTIONS Mark All As Read to mark all the alerts as read. You can also click the Dismiss icon for each alert to mark the alert as read.

Component types and metrics for alert policies

You create an alert policy for a component type. The component type drives the list of metrics to select for creating a threshold. Learn the different component types and supported metrics for each component type.

The following table lists the component types and metrics for an alert policy:

Table 1: Component Types and Metrics

Metric	Description	Suggested Alert
Topic		
UNDER REPLICATED PARTITIONS COUNT	Total number of partitions that are under replicated for a topic.	Value > 0.

Metric	Description	Suggested Alert
BYTES IN PER SEC	Bytes per second coming in to a topic.	Two kinds of alert can be configured. <ul style="list-style-type: none"> Alert-1: Value = 0, raises an alert when the topic becomes idle. Alert-2: Value > max_bytes_in_expected, raises an alert when the topic input load is higher than usual.
BYTES OUT PER SEC	Bytes per second going out from a topic. It does not count the internal replication traffic.	Two kinds of alert can be configured. <ul style="list-style-type: none"> Alert-1: Value = 0, raises an alert when the topic becomes idle. Alert-2: Value > max_bytes_out_expected, raises an alert when the topic output load is higher than usual.
OUT OF SYNC REPLICA COUNT	Total number of replicas that are not in sync with the leader for a topic.	Value > 0, raises an alert if there are out of sync replicas for the topic.
TOPIC PARTITION CONSUMPTION PERCENTAGE	Percentage of bytes consumed per topic partition compared according to the configured parameter retention.bytes. If retention.bytes is not configured, any condition involving this metric would be false.	Value > max_expected_value, raises an alert if the topic partition reaches a certain consumption percentage.
TOPIC PARTITION BYTES IN PER SEC	Bytes per second coming in to a topic partition.	Two kinds of alert can be configured. <ul style="list-style-type: none"> Alert-1: Value = 0, raises an alert when the topic partition becomes idle. Alert-2: Value > max_bytes_in_expected, raises an alert when the topic partition input load is higher than usual.
TOPIC PARTITION BYTES OUT PER SEC	Bytes per second coming out of a topic partition.	Two kinds of alert can be configured. <ul style="list-style-type: none"> Alert-1: Value = 0, raises an alert when the topic partition becomes idle. Alert-2: Value > max_bytes_out_expected, raises an alert when the topic partition output load is higher than usual.
Producer		
IS PRODUCER ACTIVE	Checks whether a producer is active.	Value is False.
MILLISECONDS LAPSED SINCE PRODUCER WAS ACTIVE	Milliseconds passed since the producer was last active.	Value > max_producer_idle_time, raises an alert if the producer did not produce for max_producer_idle_time ms.
Cluster		
ACTIVE CONTROLLER COUNT	Number of brokers in the cluster reporting as the active controller in the last interval.	Value != 1.
ONLINE BROKER COUNT	Number of brokers that are currently online.	Depends on the application. For example, you can raise an alert if the number of brokers falls below the min.insync.replicas configured for the producer. <ul style="list-style-type: none"> Alert-1: Value < min.insync.replicas, raises an alert when producer could not send any messages. Alert-2: Value = min.insync.replicas, raises an alert that denotes if any one of the remaining brokers goes down, then producer would not be able to send messages.

Metric	Description	Suggested Alert
UNCLEAN LEADER ELECTION COUNT	Number of unclean partition leader elections in the cluster reported in the last interval.	Value > 0.
UNDER REPLICATED PARTITIONS COUNT	Total number of topic partitions in the cluster that are under replicated.	Value > 0.
LEADER ELECTION PER SEC	Rate of partition leader elections.	Depends on the number of partitions in the application.
OFFLINE PARTITIONS COUNT	Total number of topic partitions, in the cluster, that are offline.	Value > 0.
NETWORK PROCESSOR AVG IDLE PERCENT	Average fraction of time the network processor threads are idle across the cluster.	<p>Two kinds of alert can be configured.</p> <ul style="list-style-type: none"> Alert-1: Value = 0, raises an alert when the network processor threads are busy. Alert-2: Value > network_processor_idle_percentage, raises an alert when the network_processor_idle_percentage is higher than usual. <p>Note: Value range is 0 to 1.</p>
REQUEST HANDLER POOL AVG IDLE PERCENT	Average fraction of time the request handler threads are idle across the cluster.	<p>Two kinds of alert can be configured.</p> <ul style="list-style-type: none"> Alert-1: Value = 0, raises an alert when the request handler threads are busy. Alert-2: Value > request_handler_idle_percentage, raises an alert when the request_handler_idle_percentage is higher than usual. <p>Note: Value range is 0 to 1.</p>
BROKER BYTES IN DEVIATION PERCENTAGE	Percentage by which a broker bytes in per second has deviated from the average bytes in per second of all the alive brokers.	Value > max_byte_in_deviation_percentage, raises an alert if a broker is seeing more than max_byte_in_deviation_percentage incoming traffic compared to average incoming traffic seen by all the brokers.
BROKER BYTES OUT DEVIATION PERCENTAGE	Percentage by which a broker bytes out per second has deviated from the average bytes out per second of all the alive brokers.	Value > max_byte_out_deviation_percentage, raises an alert if a broker is seeing more than max_byte_out_deviation_percentage outgoing traffic compared to average outgoing traffic seen by all the brokers.
ZOOKEEPER SESSION EXPIRATION PER SEC	Average rate at which brokers are experiencing zookeeper session expiration per second.	If this value is high, it can lead to controller fail over and leader changes. Raises an alert if value > 0.
Consumer		
CONSUMER GROUP LAG	How far consumer groups are behind the producers.	Depends on the application.
IS CONSUMER ACTIVE	Checks whether a consumer is active.	Value is False.
MILLISECONDS LAPSED SINCE CONSUMER WAS ACTIVE	Milliseconds passed since the consumer was last active.	Value > max_consumer_idle_time, raises an alert if the consumer did not consume for max_consumer_idle_time ms.
Broker		
BYTES IN PER SEC	Number of bytes per second produced to a broker.	<p>Two kinds of alert can be configured.</p> <ul style="list-style-type: none"> Alert-1: Value = 0, raises an alert when the broker becomes idle. Alert-2: Value > max_bytes_in_expected_per_broker, raises an alert when the broker input load is higher than usual.

Metric	Description	Suggested Alert
ZOOKEEPER SESSION EXPIRATION PER SEC	Rate at which brokers are experiencing Zookeeper session expirations per second.	If this value is high, it can lead to controller fail over and leader changes. Raises an alert if value > 0.
TOTAL PRODUCE REQUESTS PER SEC	Total number of produce requests to a broker per second.	Depends on the application. Two kinds of alert can be configured. <ul style="list-style-type: none"> Alert-1: Value =0, raises an alert when there are no produce requests for the last 15 minutes. Alert-2: Value > usual_num_producer_requests_expected to detect the spike in the number of requests.
PARTITION IMBALANCE PERCENTAGE	The partition imbalance for a broker. It is calculated as: $(\text{abs}(\text{average_no_of_partitions_per_broker} - \text{actual_no_of_partitions_per_broker}) / \text{average_no_of_partitions_per_broker}) * 100$	Value > 10 %
BYTES OUT PER SEC	Number of bytes per second fetched from a broker. It does not count the internal replication traffic.	Two kinds of alert can be configured. <ul style="list-style-type: none"> Alert-1: Value = 0, raises an alert when the broker becomes idle. Alert-2: Value > max_bytes_out_expected_per_broker, raises an alert when the broker output load is higher than usual.
IS BROKER DOWN	Checks whether a broker is down.	Value is True.
TOTAL PRODUCE REQUEST LATENCY	Latency of produce requests to this broker at the 99th percentile (in ms).	Value > max_expected_latency_ms.
ISR SHRINKS PER SEC	Rate at which brokers are experiencing InSync Replica Shrinks (number of shrinks per second).	Value > 0.
TOTAL FETCH CONSUMER REQUEST LATENCY	Latency of fetch consumer requests to this broker at 99th percentile (in ms).	Value > max_expected_latency_ms.
REQUEST HANDLER POOL AVG IDLE PERCENT	Average fraction of time the request handler threads are idle.	Two kinds of alert can be configured. <ul style="list-style-type: none"> Alert-1: Value = 0, raises an alert when the request handler threads are busy. Alert-2: Value > request_handler_idle_percentage, raises an alert when the request_handler_idle_percentage is higher than usual. Note: Value range is 0 to 1.
NETWORK PROCESSOR AVG IDLE PERCENT	Average fraction of time the network processor threads are idle.	Two kinds of alert can be configured. <ul style="list-style-type: none"> Alert-1: Value = 0, raises an alert when the network processor threads are busy. Alert-2: Value > network_processor_idle_percentage, raises an alert when the network_processor_idle_percentage is higher than usual. Note: Value range is 0 to 1.
Cluster Replication		
REPLICATION LATENCY	15 minutes average replication latency in milliseconds.	Value > max_expected_replication_latency, raises an alert if the replication latency is greater than max_expected_replication_latency.

Metric	Description	Suggested Alert
REPLICATION THROUGHPUT	15 minutes average replication throughput in bytes per second.	Value < min_expected_throughput, raises an alert if throughput during replication is low. This could happen because of network issues.
CHECKPOINT LATENCY	15 minutes average checkpoint latency in milliseconds.	Value > max_expected_checkpoint_latency, raises an alert if the checkpoint latency is greater than max_expected_replication_latency.
REPLICATION STATUS	Replication status of a replication pipeline.	Value != ACTIVE, raises an alert if the replication is not active.
Latency		
END TO END LATENCY	15 minutes average of end to end latency in ms.	Value > max_expected_latency, raises an alert if the end to end latency is greater than max_expected_latency.

Notifiers

Learn how to use notifiers to communicate important Kafka alerts to appropriate recipients.

You can configure a notifier in Streams Messaging Manager (SMM). You can modify notifier names, descriptions, and can enable or disable notifiers.

SMM uses the following predefined set of notifiers:

- Email
- HTTP

Managing alert policies and notifiers in SMM

You can use Streams Messaging Manager (SMM) to manage and monitor all the alert policies and notifiers in your environment.

Creating a notifier

Learn how to use Streams Messaging Manager (SMM) to create a notifier in your environment.


About this task

Perform the following steps to create a notifier:

Procedure

1. From the left navigation pane, select Alerts.
The Alerts Overview page appears.
2. Click NOTIFIERS.
3. Click ADD NEW to create a new notifier.
The Notifier window appears.
4. Configure the following properties:

Configuration	Property	Description
Common Notifier Configuration	NAME	Enter a unique name for the notifier.

Configuration	Property	Description
	DESCRIPTION	Enter an optional description for the notifier.
	PROVIDER	Choose one of the following providers: <ul style="list-style-type: none"> Email HTTP
	NOTIFIER RATE LIMIT COUNT	Select the number of allowed notifications.
	NOTIFIER RATE LIMIT DURATION	Select the number of allowed notifications with respect to given duration in SECONDS, MINUTES, or HOURS.
Email Notifier Configuration	FROM ADDRESS	Enter the email address to use for SMTP mail command. Default is admin@localhost.
	TO ADDRESS	Enter one or multiple email addresses that you want to send the notification to.
	USERNAME	Enter the username for SMTP.
	PASSWORD	Enter the password for SMTP. <div>  Note: The password must be reentered when editing the configuration of existing notifiers. </div>
	SMTP HOSTNAME	Enter the SMTP server that you want to connect to. Default is localhost.
	SMTP PORT	Enter the SMTP server port that you want to connect to. Default is 25.
	ENABLE AUTH	Select to enable authentication.
	ENABLE SSL/STARTTLS	Select to enable SSL. This is applicable when you enable authentication. You can either select SSL or STARTTLS.
	PROTOCOL	Enter the protocol to use to send emails. Default is SMTP.
	ENABLE DEBUG	Select to enable debug mode to trace any issue in the email notifier. Disabled by default.
HTTP Notifier Configuration	URL	Enter the target service URL.
	CONNECTION TIMEOUT (MSECS)	Select the connection timeout in milliseconds for creating the initial connection. Default is 30 seconds.
	READ TIMEOUT (MSECS)	Select the read timeout in milliseconds for waiting to read data. Default is 30 seconds.

5. Click Save.

Updating a notifier

Learn how to use Streams Messaging Manager (SMM) to update a notifier that you create in your environment.

About this task

Perform the following steps to update a notifier:

Procedure

- From the left navigation pane, select Alerts.
The Alerts Overview page appears.

2. Click NOTIFIERS.
3. Find the notifier you want to update from the list of available notifiers, and click the pencil icon beside the notifier.

The Notifier window appears.

4. Edit the properties.



Note: The password of email notifiers must be reentered when you update the configuration of the notifier.

5. Click Save.

Deleting a notifier

You can use Streams Messaging Manager (SMM) to delete a notifier that you create in your environment. You can delete a notifier only if the notifier is not mapped to an alert policy.

About this task

Perform the following steps to delete a notifier:

Procedure

1. From the left navigation pane, select Alerts.
The Alerts Overview page appears.
2. Click NOTIFIERS.
3. Find the notifier you want to delete from the list of available notifiers, and click the delete icon beside the notifier.
4. Click Yes.

Creating an alert policy

You can use Streams Messaging Manager (SMM) to create an alert policy in your environment.

About this task

Perform the following steps to create an alert policy:

Procedure

1. From the left navigation pane, select Alerts.
The Alerts Overview page appears.
2. Click ALERT POLICIES.
3. Click ADD NEW to create a new alert policy.
The Alert Policy window appears.
4. Configure the following properties:

Property	Description
NAME	Enter a unique name for the alert policy.
DESCRIPTION	Enter a description for the alert policy.
EXECUTION INTERVAL IN SECONDS	Enter the execution interval in seconds to run the alert policy periodically after the given time interval.

Property	Description
EXECUTION DELAY IN SECONDS	Enter the execution delay in seconds to delay the execution of the alert policy. This is applicable only when the last execution of the alert policy triggered an alert. Ideally, this value should not be less than the value you enter for the EXECUTION INTERVAL IN SECONDS option.
ENABLE	Choose to enable or disable the alert policy.
COMPONENT TYPE	Select one of the following component types for the IF policy: <ul style="list-style-type: none"> • Broker • Consumer • Producer • Topic • Latency • Cluster • Cluster replication
TARGET NAME	Select the target name for the IF policy. You can add multiple WITH conditions by clicking the plus icon beside TARGET NAME.
TARGET CLUSTER NAME	Select the name of the target cluster for the IF policy. The property is visible when you select Cluster replication component type.
SOURCE CLUSTER NAME	Select the name of the source cluster for the IF policy. The property is visible when you select Cluster replication component type.
TOPIC NAME	Select the topic name for the IF policy. The property is visible when you select Latency or Cluster replication component type. For Cluster replication, the topic name represents the name of the topic on the target cluster.
CONSUMER NAME	Select the consumer name for the IF policy. The property is visible when you select Latency component type.
ATTRIBUTE	Select the attribute for the policy.
CONDITION	Select the condition for the policy.
VALUE	Select the value for the policy. You can add multiple attributes, conditions, and values by clicking the plus icon beside VALUE.
NOTIFICATION	Select a notifier.
PREVIEW	Displays the alert that you configure. For example, IF [COMPONENT_TYPE]: [TARGET_NAME] has [METRIC] [CONDITION] [VALUE] THEN notify by [NOTIFICATION]

5. Click Save.

Updating an alert policy

You can use Streams Messaging Manager (SMM) to update an alert policy in your environment.

About this task

Perform the following steps to update an alert policy:

Procedure

1. From the left navigation pane, select Alerts.
The Alerts Overview page appears.
2. Click ALERT POLICIES.
3. Find the alert policy that you want to update, and click the pencil icon beside the alert policy.
The Alert Policy window appears.
4. Edit the properties.
5. Click Save.

Enabling an alert policy

You can use Streams Messaging Manager (SMM) to enable an alert policy in your environment.

About this task

Perform the following steps to enable an alert policy:

Procedure

1. From the left navigation pane, select Alerts.
The Alerts Overview page appears.
2. Click ALERT POLICIES.
3. Find the alert policy that you want to enable, and click the enable icon beside the alert policy.
The alert policy is enabled.

Disabling an alert policy

You can use Streams Messaging Manager (SMM) to disable an alert policy in your environment.

About this task

Perform the following steps to disable an alert policy:

Procedure

1. From the left navigation pane, select Alerts.
The Alerts Overview page appears.
2. Click ALERT POLICIES.
3. Find the alert policy that you want to disable, and click the enable icon beside the alert policy.
The alert policy is disabled.

Deleting an alert policy

You can use Streams Messaging Manager (SMM) to delete an alert policy in your environment.

About this task

Perform the following steps to delete an alert policy:

Procedure

1. From the left navigation pane, select Alerts.
The Alerts Overview page appears.
2. Click ALERT POLICIES.
3. Find the alert policy that you want to delete, and click the delete icon beside the alert policy.
4. Click Yes.