

Cloudera Runtime 7.0.1

Configuring Apache HBase High Availability

Date published: 2019-09-23

Date modified:

The Cloudera logo, featuring the word "CLOUDERA" in a bold, orange, sans-serif font. The letter "E" is stylized with a horizontal bar through its center.

<https://docs.cloudera.com/>

Legal Notice

© Cloudera Inc. 2025. All rights reserved.

The documentation is and contains Cloudera proprietary information protected by copyright and other intellectual property rights. No license under copyright or any other intellectual property right is granted herein.

Unless otherwise noted, scripts and sample code are licensed under the Apache License, Version 2.0.

Copyright information for Cloudera software may be found within the documentation accompanying each component in a particular release.

Cloudera software includes software from various open source or other third party projects, and may be released under the Apache Software License 2.0 (“ASLv2”), the Affero General Public License version 3 (AGPLv3), or other license terms. Other software included may be released under the terms of alternative open source licenses. Please review the license and notice files accompanying the software for additional licensing information.

Please visit the Cloudera software product page for more information on Cloudera software. For more information on Cloudera support services, please visit either the Support or Sales page. Feel free to contact us directly to discuss your specific needs.

Cloudera reserves the right to change any products at any time, and without notice. Cloudera assumes no responsibility nor liability arising from the use of products, except as expressly agreed to in writing by Cloudera.

Cloudera, Cloudera Altus, HUE, Impala, Cloudera Impala, and other Cloudera marks are registered or unregistered trademarks in the United States and other countries. All other trademarks are the property of their respective owners.

Disclaimer: EXCEPT AS EXPRESSLY PROVIDED IN A WRITTEN AGREEMENT WITH CLOUDERA, CLOUDERA DOES NOT MAKE NOR GIVE ANY REPRESENTATION, WARRANTY, NOR COVENANT OF ANY KIND, WHETHER EXPRESS OR IMPLIED, IN CONNECTION WITH CLOUDERA TECHNOLOGY OR RELATED SUPPORT PROVIDED IN CONNECTION THEREWITH. CLOUDERA DOES NOT WARRANT THAT CLOUDERA PRODUCTS NOR SOFTWARE WILL OPERATE UNINTERRUPTED NOR THAT IT WILL BE FREE FROM DEFECTS NOR ERRORS, THAT IT WILL PROTECT YOUR DATA FROM LOSS, CORRUPTION NOR UNAVAILABILITY, NOR THAT IT WILL MEET ALL OF CUSTOMER’S BUSINESS REQUIREMENTS. WITHOUT LIMITING THE FOREGOING, AND TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, CLOUDERA EXPRESSLY DISCLAIMS ANY AND ALL IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, QUALITY, NON-INFRINGEMENT, TITLE, AND FITNESS FOR A PARTICULAR PURPOSE AND ANY REPRESENTATION, WARRANTY, OR COVENANT BASED ON COURSE OF DEALING OR USAGE IN TRADE.

Contents

Enable HBase high availability using Cloudera Manager.....	4
HBase read replicas.....	4
Timeline consistency.....	5
Keep replicas current.....	5
Read replica properties.....	5
Configure read replicas using Cloudera Manager.....	6
Using rack awareness for read replicas.....	7
Create a topology map.....	7
Create a topology script.....	7
Activate read replicas on a table.....	8
Request a timeline-consistent read.....	8

Enable HBase high availability using Cloudera Manager

You can configure one or more backup Master role in Cloudera Manager to ensure that every component is highly available.

About this task

HBase administrators can configure HBase clusters with High Availability, or HA. You must configure HA when HBase applications require low-latency queries and can tolerate minimal (near-zero-second) staleness for read operations. Examples include queries on remote sensor data, distributed messaging, object stores, and user profile management.

Most aspects of HBase are highly available in a standard configuration. A cluster typically consists of one Master and three or more RegionServers. To ensure that every component is highly available, configure one or more backup Masters. The backup Masters run on other hosts than the active Master.

Procedure

1. In Cloudera Manager, select the HBase service.
2. Follow the process for adding a role instance and add a backup Master to a different host than the one on which the active Master is running.

HBase read replicas

You can configure read replicas to enable the HMaster to distribute read-only copies of regions (replicas) to different RegionServers in the cluster.

Without read replicas, only one RegionServer services a read request from a client, regardless of whether RegionServers are colocated with other DataNodes that have local access to the same block. This ensures consistency of the data being read. However, a RegionServer can become a bottleneck due to an underperforming RegionServer, network problems, or other reasons that could cause slow reads. With read replicas enabled, the HMaster distributes read-only copies of regions (replicas) to different RegionServers in the cluster. One RegionServer services the default or primary replica, which is the only replica which can service write requests. If the RegionServer servicing the primary replica is down, writes will fail. Other RegionServers serve the secondary replicas, follow the primary RegionServer and only see committed updates. The secondary replicas are read-only, and are unable to service write requests.

The secondary replicas can be kept up to date by reading the primary replica's HFiles at a set interval or by replication. If they use the first approach, the secondary replicas may not reflect the most recent updates to the data when updates are made and the RegionServer has not yet flushed the memstore to HDFS. If the client receives the read response from a secondary replica, this is indicated by marking the read as "stale". Clients can detect whether or not the read result is stale and react accordingly. Replicas are placed on different RegionServers, and on different racks when possible. This provides a measure of high availability (HA), as far as reads are concerned.

If a RegionServer becomes unavailable, the regions it was serving can still be accessed by clients even before the region is taken over by a different RegionServer, using one of the secondary replicas. The reads may be stale until the entire WAL is processed by the new RegionServer for a given region. For any given read request, a client can request a faster result even if it comes from a secondary replica, or if consistency is more important than speed, it can ensure that its request is serviced by the primary RegionServer. This allows you to decide the relative importance of consistency and availability, in terms of the CAP Theorem, in the context of your application, or individual aspects of your application, using Timeline Consistency semantics.

Timeline consistency

You can change your consistency level to **TIMELINE** to allow a more flexible standard of consistency than the default HBase model of **STRONG** consistency.

A client can indicate the level of consistency it requires for a given read (Get or Scan) operation. The default consistency level is **STRONG**, meaning that the read request is only sent to the **RegionServer** servicing the region. This is the same behavior as when read replicas are not used. The other possibility, **TIMELINE**, sends the request to all **RegionServers** with replicas, including the primary. The client accepts the first response, which includes whether it came from the primary or a secondary **RegionServer**. If it came from a secondary, the client can choose to verify the read later or not to treat it as definitive.

Keep replicas current

You can choose from two different mechanisms for keeping replicas up to date: using a timer or using replication.

Using a Timer: In this mode, replicas are refreshed at a time interval controlled by the configuration option `hbase.regionserver.storefile.refresh.period`.

Using Replication: In this mode, replicas are kept current between a source and sink cluster using HBase replication. The sink cluster in this cluster is just the read replicas in the same HBase cluster. This can potentially allow for faster synchronization than using a timer. Each time a flush occurs on the source cluster, a notification is pushed to the sink clusters for the table. To use replication to keep replicas current, you must first set the column family attribute `REGION_MEMSTORE_REPLICATION` to false, then set the HBase configuration property `hbase.region.replica.replication.enabled` to true.



Note: Read-replica updates using replication are not supported for the `hbase:meta` table. Columns of `hbase:meta` must always have their `REGION_MEMSTORE_REPLICATION` attribute set to false.

Read replica properties

You must understand the various properties to configure to enable support for read replicas in HBase.

Table 1: HBase Read Replica Properties

Property Name	Default Value	Description
<code>hbase.region.replica.replication.enabled</code>	false	The mechanism for refreshing the secondary replicas. If set to false, secondary replicas are not guaranteed to be consistent at the row level. Secondary replicas are refreshed at intervals controlled by a timer (<code>hbase.regionserver.storefile.refresh.period</code>), and so are guaranteed to be at most that interval of milliseconds behind the primary RegionServer. Secondary replicas read from the HFile in HDFS, and have no access to writes that have not been flushed to the HFile by the primary RegionServer. If true, replicas are kept up to date using replication. and the column family has the attribute <code>REGION_MEMSTORE_REPLICATION</code> set to false. Using replication for read replication of <code>hbase:meta</code> is not supported, and <code>REGION_MEMSTORE_REPLICATION</code> must always be set to false on the column family.

Property Name	Default Value	Description
hbase.regionserver.storefile.refresh.period	0 (disabled)	The period, in milliseconds, for refreshing the store files for the secondary replicas. The default value of 0 indicates that the feature is disabled. Secondary replicas update their store files from the primary RegionServer at this interval. If refreshes occur too often, this can create a burden for the NameNode. If refreshes occur too infrequently, secondary replicas will be less consistent with the primary RegionServer.
hbase.ipc.client.allowsInterrupt	true	Whether or not to enable interruption of RPC threads at the client. The default value of true enables primary RegionServers to access data from other regions' secondary replicas.
hbase.client.primaryCallTimeout.get	10 ms	The timeout period, in milliseconds, an HBase client's will wait for a response before the read is submitted to a secondary replica if the read request allows timeline consistency. The default value is 10. Lower values increase the number of remote procedure calls while lowering latency.
hbase.client.primaryCallTimeout.multiget	10 ms	The timeout period, in milliseconds, before an HBase client's multi-get request, such as HTable.get(List<GET>)), is submitted to a secondary replica if the multi-get request allows timeline consistency. Lower values increase the number of remote procedure calls while lowering latency.

Configure read replicas using Cloudera Manager

You can configure read replicas using Cloudera Manager.

Procedure

1. Before you can use replication to keep replicas current, you must set the column attribute `REGION_MEMSTORE_REPLICATION` to false for the HBase table, using HBase Shell or the client API.
2. In Cloudera Manager, select the HBase service.
3. Click the Configuration tab.
4. Select Scope > HBase or HBase Service-Wide .
5. Select Category > Advanced .
6. Locate the HBase Service Advanced Configuration Snippet (Safety Valve) for hbase-site.xml property or search for it by typing its name in the Search box.
7. Create a configuration and paste it into the text field. The following example configuration demonstrates the syntax:

```
<property>
  <name>hbase.regionserver.storefile.refresh.period</name>
  <value>0</value>
</property>
<property>
  <name>hbase.ipc.client.allowsInterrupt</name>
  <value>true</value>
  <description>Whether to enable interruption of RPC threads at the client
. The default value of true is
  required to enable Primary RegionServers to access other RegionServers
  in secondary mode. </description>
</property>
```

```
<property>
  <name>hbase.client.primaryCallTimeout.get</name>
  <value>10</value>
</property>
<property>
  <name>hbase.client.primaryCallTimeout.multiget</name>
  <value>10</value>
</property>
```

8. Click Save Changes to commit the changes.
9. Restart the HBase service.

Using rack awareness for read replicas

Rack awareness for read replicas is modeled after the mechanism used for rack awareness in Hadoop.

The default implementation, which you can override by setting `hbase.util.ip.to.rack.determiner`, to custom implementation, is `ScriptBasedMapping`, which uses a topology map and a topology script to enforce distribution of the replicas across racks.

Create a topology map

The topology map assigns hosts to racks. You can create a topology map using Cloudera Manager.

About this task

The topology map assigns hosts to racks. It is read by the topology script. A rack is a logical grouping, and does not necessarily correspond to physical hardware or location. Racks can be nested. If a host is not in the topology map, it is assumed to be a member of the default rack. The following map uses a nested structure, with two data centers which each have two racks. All services on a host that are rack-aware will be affected by the rack settings for the host.

Procedure

- If you use Cloudera Manager, do not create the map manually. Instead, go to Hosts, select the hosts to assign to a rack, and select **Actions for Selected > Assign Rack**.

```
<topology>
  <node name="host1.example.com" rack="/dc1/r1"/>
  <node name="host2.example.com" rack="/dc1/r1"/>
  <node name="host3.example.com" rack="/dc1/r2"/>
  <node name="host4.example.com" rack="/dc1/r2"/>
  <node name="host5.example.com" rack="/dc2/r1"/>
  <node name="host6.example.com" rack="/dc2/r1"/>
  <node name="host7.example.com" rack="/dc2/r2"/>
  <node name="host8.example.com" rack="/dc2/r2"/>
</topology>
```

Create a topology script

The topology script determines rack topology using the topology map.

About this task

The topology script determines rack topology using the topology map. By default, CDH uses `/etc/hadoop/conf.cloudera.YARN-1/topology.py`

Procedure

- To use a different script, set `net.topology.script.file.name` to the absolute path of the topology script.

Activate read replicas on a table

After enabling read replica support on your RegionServers, configure the tables for which you want read replicas to be created.

About this task

After enabling read replica support on your RegionServers, configure the tables for which you want read replicas to be created.

Procedure

- At table creation, to create a new table with read replication capabilities enabled, set the `REGION_REPLICATION` property on the table. Use a command like the following, in HBase Shell:

```
hbase> create 'myTable', 'myCF', {REGION_REPLICATION => '3'}
```

- By altering an existing table, you can also alter an existing column family to enable or change the number of read replicas it propagates, using a command similar to the following. The change will take effect at the next major compaction.

```
hbase> disable 'myTable'  
hbase> alter 'myTable', 'myCF', {REGION_REPLICATION => '3'}  
hbase> enable 'myTable'
```

Request a timeline-consistent read

You can use request a timeline-consistent read in your application.

About this task

To request a timeline-consistent read in your application, use the `get.setConsistency(Consistency.TIMELINE)` method before performing the Get or Scan operation.

To check whether the result is stale (comes from a secondary replica), use the `isStale()` method of the result object. Use the following examples for reference.

Procedure

- Get request

```
Get get = new Get(key);  
get.setConsistency(Consistency.TIMELINE);  
Result result = table.get(get);
```

- Scan request

```
Scan scan = new Scan();  
scan.setConsistency(CONSISTENCY.TIMELINE);  
ResultScanner scanner = table.getScanner(scan);  
Result result = scanner.next();
```

- Scan request to a specific replica.

This example overrides the normal behavior of sending the read request to all known replicas, and only sends it to the replica specified by ID.

```
Scan scan = new Scan();
scan.setConsistency(CONSISTENCY.TIMELINE);
scan.setReplicaId(2);
ResultScanner scanner = table.getScanner(scan);
Result result = scanner.next();
```

- Detect a stale result

You can also request timeline consistency using HBase Shell, allowing the result to come from a secondary replica.

```
hbase> get 'myTable', 'myRow', {CONSISTENCY => "TIMELINE"}
hbase> scan 'myTable', {CONSISTENCY => 'TIMELINE'}
```