

Accessing Cloud Data

Date published: 2019-09-23

Date modified: 2021-06-09



Legal Notice

© Cloudera Inc. 2025. All rights reserved.

The documentation is and contains Cloudera proprietary information protected by copyright and other intellectual property rights. No license under copyright or any other intellectual property right is granted herein.

Unless otherwise noted, scripts and sample code are licensed under the Apache License, Version 2.0.

Copyright information for Cloudera software may be found within the documentation accompanying each component in a particular release.

Cloudera software includes software from various open source or other third party projects, and may be released under the Apache Software License 2.0 (“ASLv2”), the Affero General Public License version 3 (AGPLv3), or other license terms. Other software included may be released under the terms of alternative open source licenses. Please review the license and notice files accompanying the software for additional licensing information.

Please visit the Cloudera software product page for more information on Cloudera software. For more information on Cloudera support services, please visit either the Support or Sales page. Feel free to contact us directly to discuss your specific needs.

Cloudera reserves the right to change any products at any time, and without notice. Cloudera assumes no responsibility nor liability arising from the use of products, except as expressly agreed to in writing by Cloudera.

Cloudera, Cloudera Altus, HUE, Impala, Cloudera Impala, and other Cloudera marks are registered or unregistered trademarks in the United States and other countries. All other trademarks are the property of their respective owners.

Disclaimer: EXCEPT AS EXPRESSLY PROVIDED IN A WRITTEN AGREEMENT WITH CLOUDERA, CLOUDERA DOES NOT MAKE NOR GIVE ANY REPRESENTATION, WARRANTY, NOR COVENANT OF ANY KIND, WHETHER EXPRESS OR IMPLIED, IN CONNECTION WITH CLOUDERA TECHNOLOGY OR RELATED SUPPORT PROVIDED IN CONNECTION THEREWITH. CLOUDERA DOES NOT WARRANT THAT CLOUDERA PRODUCTS NOR SOFTWARE WILL OPERATE UNINTERRUPTED NOR THAT IT WILL BE FREE FROM DEFECTS NOR ERRORS, THAT IT WILL PROTECT YOUR DATA FROM LOSS, CORRUPTION NOR UNAVAILABILITY, NOR THAT IT WILL MEET ALL OF CUSTOMER’S BUSINESS REQUIREMENTS. WITHOUT LIMITING THE FOREGOING, AND TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, CLOUDERA EXPRESSLY DISCLAIMS ANY AND ALL IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, QUALITY, NON-INFRINGEMENT, TITLE, AND FITNESS FOR A PARTICULAR PURPOSE AND ANY REPRESENTATION, WARRANTY, OR COVENANT BASED ON COURSE OF DEALING OR USAGE IN TRADE.

Contents

Cloud storage connectors overview.....	5
The Cloud Storage Connectors.....	5
Working with Amazon S3.....	6
Limitations of Amazon S3.....	7
Configuring Access to S3.....	7
Configuring Access to S3 on CDP Public Cloud.....	8
Configuring Access to S3 on CDP Private Cloud Base.....	8
Using EC2 Instance Metadata to Authenticate.....	10
Referencing S3 Data in Applications.....	10
Configuring Per-Bucket Settings.....	11
Customizing Per-Bucket Secrets Held in Credential Files.....	12
Configuring Per-Bucket Settings to Access Data Around the World.....	12
Encrypting Data on S3.....	13
SSE-S3: Amazon S3-Managed Encryption Keys.....	13
SSE-KMS: Amazon S3-KMS Managed Encryption Keys.....	13
SSE-C: Server-Side Encryption with Customer-Provided Encryption Keys.....	15
Configuring Encryption for Specific Buckets.....	15
Encrypting an S3 Bucket with Amazon S3 Default Encryption.....	15
Performance Impact of Encryption.....	16
Using S3Guard for Consistent S3 Metadata.....	16
Introduction to S3Guard.....	16
Configuring S3Guard.....	18
Monitoring and Maintaining S3Guard.....	23
Disabling S3Guard and destroying a table.....	23
Pruning Old Data from S3Guard Tables.....	23
Importing a Bucket into S3Guard.....	24
Verifying that S3Guard is Enabled on a Bucket.....	24
Using the S3Guard CLI.....	25
S3Guard: Operational Issues.....	25
Safely Writing to S3 Through the S3A Committers.....	26
Introducing the S3A Committers.....	26
Configuring Directories for Intermediate Data.....	27
Using the Directory Committer in MapReduce.....	28
Verifying That an S3A Committer Was Used.....	28
Cleaning up after failed jobs.....	28
Using the S3Guard Command to List and Delete Uploads.....	28
Advanced Committer Configuration.....	29
Securing the S3A Committers.....	30
The S3A Committers and Third-Party Object Stores.....	30
Limitations of the S3A Committers.....	30
Troubleshooting the S3A Committers.....	31
Security Model and Operations on S3.....	31
S3A and Checksums (Advanced Feature).....	32
A List of S3A Configuration Properties.....	33
Working with versioned S3 buckets.....	33

Working with Third-party S3-compatible Object Stores.....	34
Improving Performance for S3A.....	35
Working with S3 buckets in the same AWS region.....	35
Configuring and tuning S3A block upload.....	35
Optimizing S3A read performance for different file types.....	38
S3 Performance Checklist.....	39
Troubleshooting S3 and S3Guard.....	39

Working with Google Cloud Storage..... 39

Configuring Access to Google Cloud Storage.....	40
Create a GCP Service Account.....	40
Create a Custom Role.....	41
Modify GCS Bucket Permissions.....	42
Configure Access to GCS from Your Cluster.....	43
Additional Configuration Options for GCS.....	44

Working with the ABFS Connector..... 44

Introduction to Azure Storage and the ABFS Connector.....	45
Feature Comparisons.....	45
Setting up and configuring the ABFS connector.....	46
Configuring the ABFS Connector.....	46
Authenticating with ADLS Gen2.....	47
ADLS Proxy Setup.....	49
Performance and Scalability.....	49
Hierarchical namespaces vs. non-namespaces.....	49
Flush options.....	51
Using ABFS using CLI.....	51
Hadoop File System commands.....	51
Create a table in Hive.....	52
Accessing Azure Storage account container from spark-shell.....	53
Copying data with Hadoop DistCp.....	54
DistCp and Proxy Settings.....	55
ADLS Trash Folder Behavior.....	55
Troubleshooting ABFS.....	55

Cloud storage connectors overview

This content provides information and steps required for, using, securing, tuning performance, and troubleshooting access to the cloud storage services using CDP cloud storage connectors available for Amazon Web Services (Amazon S3). This content provides information and steps required for, using, securing, tuning performance, and troubleshooting access to the cloud storage services using CDP cloud storage connectors available for Amazon Web Services (Amazon S3) and Microsoft Azure (ADLS Gen 2).

The primary audience of this content are the administrators and users of CDP deployed on cloud Infrastructure-as-a-Service (IaaS) such as Amazon Web Services (AWS). The primary audience of this content are the administrators and users of CDP deployed on cloud Infrastructure-as-a-Service (IaaS) such as Amazon Web Services (AWS) and Microsoft Azure.

You may also use this content if your CDP is deployed in your own data center and you plan to access cloud storage through the connectors; however, your experience and performance may vary based on the network bandwidth between your data center and the cloud storage service. In addition, you can optionally configure other features where available.

The Cloud Storage Connectors


When deploying CDP clusters on cloud IaaS, you can take advantage of the native integration with the object storage services available on Amazon S3 on AWS. This integration is through cloud storage connectors included with CDP. Their primary function is to help you connect to, access, and work with data the cloud storage services.

The cloud connectors allow you to access and work with data stored in Amazon S3, including but not limited to the following use cases:

- Collect data for analysis and then load it into Hadoop ecosystem applications such as Hive or Spark directly from cloud storage services.
- Persist data to cloud storage services for use outside of CDP clusters.
- Copy data stored in cloud storage services to HDFS for analysis and then copy back to the cloud when done.
- Share data between multiple CDP clusters – and between various external non-CDP systems.
- Back up CDP clusters using distcp.

The cloud object store connectors are implemented as individual Hadoop modules. The libraries and their dependencies are automatically placed on the classpath.

Hadoop Ecosystem Applications (Hive queries, MapReduce, Spark, etc.)



Amazon S3 is an object store. The S3A connector implements the Hadoop filesystem interface using AWS Java SDK to access the web service, and provides Hadoop applications with a filesystem view of the buckets. Applications can manipulate data stored in Amazon S3 buckets with an URL starting with the `s3a://` prefix.

Amazon S3 can not be used as a replacement for HDFS as the cluster filesystem in CDP. Amazon S3 can be used as a source and destination of work.

Working with Amazon S3

The [Amazon S3](#) object store is the standard mechanism to store, retrieve, and share large quantities of data in AWS.

The features of Amazon S3 include:

- Object store model for storing, listing, and retrieving data.
- Support for objects up to 5 terabytes, with many petabytes of data allowed in a single "bucket".
- Data is stored in Amazon S3 in [buckets](#) which are stored in different [AWS regions](#).
- Buckets can be restricted to different users or [IAM roles](#).
- Data stored in an Amazon S3 bucket is billed based on the size of data how long it is stored, and on operations accessing this data. In addition, you are billed when you transfer data between regions:
 - Data transfers between an Amazon S3 bucket and a cluster running in the same region are free of download charges (except in the special case of buckets in which data is served on a user-pays basis).
 - Data downloaded from an Amazon S3 bucket located outside the region in which the bucket is hosted is billed per megabyte.
 - Data downloaded from an Amazon S3 bucket to any host over the internet is also billed per-Megabyte.
- Data stored in Amazon S3 can be backed up with [Amazon Glacier](#).

The Hadoop client to S3, called "S3A", makes the contents of a bucket appear like a filesystem, with directories, files in the directories, and operations on directories and files. As a result, applications which can work with data stored in HDFS can also work with data stored in S3. However, since S3 is an object store, it has certain limitations that you should be aware of.

Limitations of Amazon S3

Even though Hadoop's S3A client can make an S3 bucket appear to be a Hadoop-compatible filesystem, it is still an object store, and has some limitations when acting as a Hadoop-compatible filesystem.

The key things to be aware of are:

- Operations on directories are potentially slow and non-atomic.
- Not all file operations are supported. In particular, some file operations needed by Apache HBase are not available — so HBase cannot be run on top of Amazon S3 without additional features provided by a service such as S3Guard. HBase Object Store Semantics (HBOSS) adapter bridges the gap between HBase and the S3A filesystem. HBOSS depends on S3Guard for accessing S3A buckets, so ensure that the given cluster and target AWS account fulfill all S3Guard requirements.
- Data is not visible in the object store until the entire output stream has been written.
- Neither the per-file and per-directory permissions supported by HDFS nor its more sophisticated ACL mechanism are supported.
- Bandwidth between your workload clusters and Amazon S3 is limited and can vary significantly depending on network and VM load.

For these reasons, while Amazon S3 can be used as the source and store for persistent data, it cannot be used as a direct replacement for a cluster-wide filesystem such as HDFS, or be used as defaultFS.

Configuring Access to S3

IDBroker is a REST API built as part of Apache Knox's authentication services. It allows an authenticated user to exchange a set of credentials or a token for cloud vendor access tokens. It manages mapping LDAP users to FreeIPA cloud identities for data access. It performs identity mapping for access to object stores.

This section provides information about the options that are enabled by default. For information on how IDBroker works in CDP, see [Cloud identity federation](#) in the *Management Console* documentation.

For Apache Hadoop applications to be able to interact with Amazon S3, they must know the AWS access key and the secret key. This can be achieved in multiple ways, including configuration properties, environment variables, and EC2 instance metadata. While the first two options can be used when accessing S3 from a cluster running in your own data center. IAM roles, which use instance metadata should be used to control access to AWS resources if your cluster is running on EC2.

Deployment Scenario	Authentication Options
Cluster runs on EC2	Use IAM roles to bind your EC2 VMs to a specific role, and so manage its access to AWS resources. IDBroker will provide authenticated users with the AWS credentials they need to access data in S3. There is no need to manually provide any AWS login credentials directly to users
Cluster runs in your own data center	Use configuration properties to authenticate. You can set the configuration properties globally or per-bucket.

Temporary security credentials, also known as "session credentials", can be issued. These consist of a secret key with a limited lifespan, along with a session token, another secret which must be known and used alongside the access key. The secret key is never passed to AWS services directly. Instead it is used to [sign the URL and headers of the HTTP request](#).

By default, the S3A filesystem client follows the following authentication chain:

1. The AWS login details are looked for in the job configuration settings.
2. The AWS environment variables are then looked for.

3. An attempt is made to query the Amazon EC2 Instance Metadata Service to retrieve credentials published to EC2 VMs.

Configuring Access to S3 on CDP Public Cloud

IDBroker is a REST API built as part of Apache Knox's authentication services. It allows an authenticated user to exchange a set of credentials or a token for cloud vendor access tokens. It manages mapping LDAP users to FreeIPA cloud identities for data access. It performs identity mapping for access to object stores.

This section provides information about the options that are enabled by default. For information on how IDBroker works in CDP, see [Cloud identity federation](#) in the *Management Console* documentation.

For Apache Hadoop applications to be able to interact with Amazon S3, they must know the AWS access key and the secret key. This can be achieved in multiple ways, including configuration properties, environment variables, and EC2 instance metadata. While the first two options can be used when accessing S3 from a cluster running in your own data center. IAM roles, which use instance metadata should be used to control access to AWS resources if your cluster is running on EC2.

Deployment Scenario	Authentication Options
Cluster runs on EC2	Use IAM roles to bind your EC2 VMs to a specific role, and so manage its access to AWS resources. IDBroker will provide authenticated users with the AWS credentials they need to access data in S3. There is no need to manually provide any AWS login credentials directly to users
Cluster runs in your own data center	Use configuration properties to authenticate. You can set the configuration properties globally or per-bucket.

Temporary security credentials, also known as "session credentials", can be issued. These consist of a secret key with a limited lifespan, along with a session token, another secret which must be known and used alongside the access key. The secret key is never passed to AWS services directly. Instead it is used to [sign the URL and headers of the HTTP request](#).

By default, the S3A filesystem client follows the following authentication chain:

1. The AWS login details are looked for in the job configuration settings.
2. The AWS environment variables are then looked for.
3. An attempt is made to query the Amazon EC2 Instance Metadata Service to retrieve credentials published to EC2 VMs.

Configuring Access to S3 on CDP Private Cloud Base

For Apache Hadoop applications to be able to interact with Amazon S3, they must know the AWS access key and the secret key. This can be achieved in three different ways: through [configuration properties](#), [environment variables](#), or [instance metadata](#). While the first two options can be used when accessing S3 from a cluster running in your own data center. IAM roles, which use instance metadata should be used to control access to AWS resources if your cluster is running on EC2.

Table 1: Authentication Options for Different Deployment Scenarios

Deployment Scenario	Authentication Options
Cluster runs on EC2	Use IAM roles to control access to your AWS resources. If you configure role-based access, instance metadata will automatically be used to authenticate.
Cluster runs in your own data center	Use the configuration properties to authenticate. You can set the configuration properties globally or per-bucket .

[Temporary security credentials](#), also known as session credentials, can be issued. These consist of a secret key with a limited lifespan, along with a session token, another secret which must be known and used alongside the access key.

The secret key is never passed to AWS services directly. Instead it is used to [sign the URL and headers of the HTTP request](#).

By default, the S3A filesystem client follows the following authentication chain:

1. The `fs.s3a.access.key` and `fs.s3a.secret.key` are looked for in the Hadoop configuration properties.
2. The AWS environment variables are then looked for.
3. An attempt is made to query the Amazon EC2 Instance Metadata Service to retrieve credentials published to EC2 VMs.

Using Configuration Properties to Authenticate

To configure authentication with S3, explicitly declare the credentials in a configuration file such as `core-site.xml`.

```
<property>
  <name>fs.s3a.access.key</name>
  <value>ACCESS-KEY</value>
</property>

<property>
  <name>fs.s3a.secret.key</name>
  <value>SECRET-KEY</value>
</property>
```

If using AWS session credentials for authentication, the secret key must be that of the session, and the `fs.s3a.session.token` option set to your session token.

```
<property>
  <name>fs.s3a.session.token</name>
  <value>SESSION-TOKEN</value>
</property>
```

This configuration can be added for a specific bucket. For more information, see [Using Per-Bucket Credentials to Authenticate](#).

To protect these credentials, we recommend that you use the [credential provider](#) framework to securely store and access your credentials.

To validate that you can successfully authenticate with S3, try [referencing S3 in a URL](#).

Using Per-Bucket Credentials to Authenticate

S3A supports per-bucket configuration, which can be used to declare different authentication credentials and authentication mechanisms for different buckets. For example, a bucket `s3a://nightly/` used for nightly data can be configured with a session key.

```
<property>
  <name>fs.s3a.bucket.nightly.access.key</name>
  <value>AKAAACCESSKEY-2</value>
</property>

<property>
  <name>fs.s3a.bucket.nightly.secret.key</name>
  <value>SESSIONSECRETKEY</value>
</property>
```

Similarly, you can set a session token for a specific bucket:

```
<property>
  <name>fs.s3a.bucket.nightly.session.token</name>
  <value>SESSION-TOKEN</value>
</property>
```

This technique is useful for working with external sources of data, or when copying data between buckets belonging to different accounts.

Using Environment Variables to Authenticate

AWS CLI supports authentication through [environment variables](#). These same environment variables will be used by Hadoop if no configuration properties are set.

The environment variables are:

Environment Variable	Description
AWS_ACCESS_KEY_ID	Access key
AWS_SECRET_ACCESS_KEY	Secret key
AWS_SESSION_TOKEN	Session token (only if using session authentication)

Using EC2 Instance Metadata to Authenticate

If your cluster is running on EC2, the standard way to manage access is via [Amazon Identity and Access Management \(IAM\)](#), which allows you to create users, groups, and roles to control access to services such as Amazon S3 via attached policies.

A role does not have any credentials such as password or access keys associated with it. Instead, if a user is assigned to a role, access keys are generated dynamically and provided to the user when needed. For more information, refer to [IAM Roles for Amazon EC2](#) in Amazon documentation.

When launching your cluster on EC2, specify an IAM role that you want to use; if you are planning to use S3 with your cluster, make sure that the role associated with the cluster includes a policy that grants access to S3. For more information, refer to [Using an IAM Role to Grant Permissions to Applications Running on Amazon EC2 Instances](#) in Amazon documentation. No additional configuration is required.



Note: You can use IAM Roles to control access to keys stored in Amazon's KMS Key Management service. For more information, refer to [Overview of Managing Access to Your AWS KMS Resources](#) in Amazon documentation.

Referencing S3 Data in Applications

You can reference data in Amazon S3 using a URL starting with the `s3a://` prefix followed by bucket name and path to file or directory.

The URL structure is:

```
s3a://<bucket>/<dir>/<file>
```

For example, to access a file called "mytestfile" in a directory called "mytestdir", which is stored in a bucket called "mytestbucket", the URL is:

```
s3a://mytestbucket/mytestdir/mytestfile
```

The following FileSystem shell commands demonstrate access to a bucket named mytestbucket:

```
hadoop fs -ls s3a://mytestbucket/
hadoop fs -mkdir s3a://mytestbucket/testDir
hadoop fs -put testFile s3a://mytestbucket/testFile
hadoop fs -cat s3a://mytestbucket/testFile
```

Configuring Per-Bucket Settings

You can specify bucket-specific configuration values which override the common configuration values.

1. Authentication mechanisms and credentials
2. Encryption settings
3. The specific S3 endpoints to send HTTP requests to. This is essential when working with S3 regions which only support the "V4 authentication API", in case of which callers must always declare the explicit region.

All fs.s3a options other than a small set of unmodifiable values (currently fs.s3a.impl) can be set on a per-bucket basis.

To set a bucket-specific option:

1. Add a new configuration, replacing the fs.s3a. prefix on an option with fs.s3a.bucket.BUCKETNAME, where BUCKETNAME is the name of the bucket.

For example, if you are configuring access key for a bucket called "nightly", instead of using fs.s3a.access.key property name, use fs.s3a.bucket.nightly.access.key.

2. When connecting to a bucket, all options explicitly set for that bucket will override the base fs.s3a. values, but they will not be picked up by other buckets.

Example

You may have a base configuration to use the IAM role information available when deployed in Amazon EC2 VM or an AWS container service.

```
<property>
  <name>fs.s3a.aws.credentials.provider</name>
  <value>org.apache.hadoop.fs.s3a.auth.IAMInstanceCredentialsProvider</value>
</property>
```

This will be the default authentication mechanism for S3A buckets.

A bucket s3a://nightly/ used for nightly data uses a session key, so its bucket-specific configuration is:

```
<property>
  <name>fs.s3a.bucket.nightly.access.key</name>
  <value>AKAACCESS-SKEY-2</value>
</property>
<property>
  <name>fs.s3a.bucket.nightly.secret.key</name>
  <value>SESSION-SECRET-KEY</value>
</property>
<property>
  <name>fs.s3a.bucket.nightly.session.token</name>
  <value>SHORT-LIVED-SESSION-TOKEN</value>
</property>

<property>
  <name>fs.s3a.bucket.nightly.aws.credentials.provider</name>
  <value>org.apache.hadoop.fs.s3a.TemporaryAWSCredentialsProvider</value>
</property>
```

Finally, the public s3a://landsat-pds/ bucket could be accessed anonymously, so its bucket-specific configuration is:

```
<property>
  <name>fs.s3a.bucket.landsat-pds.aws.credentials.provider</name>
  <value>org.apache.hadoop.fs.s3a.AnonymousAWSCredentialsProvider</value>
</property>
```

For all other buckets, the base configuration is used.

Customizing Per-Bucket Secrets Held in Credential Files

JCEKS credential files support the same per-bucket settings as those in XML files. To provide different credentials for different buckets, simply create per-bucket entries in the JCEKS file with the relevant secrets.

Example

1. Set base properties for `fs.s3a.secret.key` and `fs.s3a.access.key` in the JCEKS file. These will be the default.
2. Set all non-security properties per-bucket for a bucket called "frankfurt-1" in the `core-site.xml`. These will override the base properties when talking to the bucket "frankfurt-1".
3. For the AWS authentication secrets, set the `fs.s3a.frankfurt-1.access.key` and `fs.s3a.frankfurt-1.secret.key` properties in the JCEKS file.

Related Information

[Credential Provider API Guide](#)

Configuring Per-Bucket Settings to Access Data Around the World

S3 buckets are hosted in different AWS regions, the default being "US-East". The S3A client talks to this region by default, issuing HTTP requests to the server `s3.amazonaws.com`. This central endpoint can be used for accessing any bucket in any region which supports using the V2 Authentication API, albeit possibly at a reduced performance.

Each region has its own S3 endpoint, [documented by Amazon](#). The S3A client supports these endpoints. While it is generally simpler to use the default endpoint, direct connections to specific regions (i.e. connections via region's own endpoint) may deliver performance and availability improvements, and are mandatory when working with the most recently deployed regions, such as Frankfurt and Seoul.

When deciding which endpoint to use, consider the following:

1. Applications running in EC2 infrastructure do not pay for data transfers to or from local S3 buckets. In contrast, they will be billed for access to remote buckets. Therefore, wherever possible, always use local buckets and local copies of data.
2. When the V1 request signing protocol is used, the default S3 endpoint can support data transfer with any bucket.
3. When the V4 request signing protocol is used, AWS requires the explicit region endpoint to be used — hence S3A must be configured to use the specific endpoint. This is done in the configuration option `fs.s3a.endpoint`.
4. All endpoints other than the default endpoint only support interaction with buckets local to that S3 instance.

If the wrong endpoint is used, the request may fail. This may be reported as a 301 redirect error, or as a 400 Bad Request. Take these failures as cues to check the endpoint setting of a bucket.

The up to date list of endpoints is provided by Amazon: https://docs.aws.amazon.com/general/latest/gr/rande.html#s3_region

Example

The following examples show per-bucket endpoints set for the "landsat-pds" and "eu-dataset" buckets, with the endpoints set to the default central endpoint and EU/Ireland, respectively:

```
<property>
  <name>fs.s3a.bucket.landsat-pds.endpoint</name>
  <value>s3.amazonaws.com</value>
  <description>The endpoint for s3a://landsat-pds URLs</description>
</property>
<property>
  <name>fs.s3a.bucket.eu-dataset.endpoint</name>
  <value>s3-eu-west-1.amazonaws.com</value>
  <description>The endpoint for s3a://eu-dataset URLs</description>
</property>
```

Explicitly declaring a bucket bound to the central endpoint ensures that if the default endpoint is changed to a new region, data stored in US-east is still reachable.

Encrypting Data on S3

Amazon S3 supports a number of encryption mechanisms to better secure the data in S3.

- In [Server-Side Encryption \(SSE\)](#), the data is encrypted before it is saved to disk in S3, and decrypted when it is read. This encryption and decryption takes place in the S3 infrastructure, and is transparent to (authenticated) clients.
- In [Client-Side Encryption \(CSE\)](#), the data is encrypted and decrypted on the client, that is, inside the AWS S3 SDK. This mechanism is not supported in Hadoop due to incompatibilities with most applications. Specifically, the amount of decrypted data is often less than the file length, breaking all the code which assumes that the content of a file is the same size as that stated in directory listings.



Note: CDP *only* supports Server-Side Encryption (SSE) and *does not* support Client-Side Encryption (CSE).

For this server-side encryption to work, the S3 servers require secret keys to encrypt data, and the same secret keys to decrypt it. These keys can be managed in three ways:

- SSE-S3: By using Amazon S3-Managed Keys
- SSE-KMS: By using AWS Key Management Service
- SSE-C: By using customer-supplied keys

In general, the specific configuration mechanism can be set via the property `fs.s3a.server-side-encryption-algorithm` in `core-site.xml`. However, some encryption options require extra settings. Server Side encryption slightly slows down performance when reading data from S3.

It is possible to configure encryption for specific buckets and to mandate encryption for a specific S3 bucket.

Related Information

[Troubleshooting S3 and S3Guard](#)

SSE-S3: Amazon S3-Managed Encryption Keys

In SSE-S3, all keys and secrets are managed inside S3. This is the simplest encryption mechanism.

Enabling SSE-S3

To write S3-SSE encrypted files, the value of `fs.s3a.server-side-encryption-algorithm` must be set to that of the encryption mechanism used in `core-site.xml`; currently only AES256 is supported.

```
<property>
  <name>fs.s3a.server-side-encryption-algorithm</name>
  <value>AES256</value>
</property>
```

Once set, all new data will be uploaded encrypted. There is no need to set this property when downloading data — the data will be automatically decrypted when read using the Amazon S3-managed key.

To learn more, refer to [Protecting Data Using Server-Side Encryption with Amazon S3-Managed Encryption Keys \(SSE-S3\)](#) in AWS documentation.



Note: When encrypted files are renamed, they are de-encrypted and then re-encrypted with the encryption settings algorithm of the client application performing the rename. If a client with encryption disabled renames an encrypted file, the new file will be unencrypted.

SSE-KMS: Amazon S3-KMS Managed Encryption Keys

Amazon offers a pay-per-use key management service, [AWS KMS](#). This service can be used to encrypt data on S3 using keys which can be centrally managed and assigned to specific roles and IAM accounts.

The AWS KMS [can be used by S3 to encrypt uploaded data](#). When uploading data encrypted with SSE-KMS, the named key that was used to encrypt the data is retrieved from the KMS service, and used to encode the per-object secret which encrypts the uploaded data. To decode the data, the same key must be retrieved from KMS and used to unencrypt the per-object secret key, which is then used to decode the actual file.

KMS keys can be managed by an organization's administrators in AWS, including having access permissions assigned and removed from specific users, groups, and IAM roles. Only those "principals" with granted rights to a key may access it, hence only they may encrypt data with the key, and decrypt data encrypted with it. This allows KMS to be used to provide a cryptographically secure access control mechanism for data stores on S3.

**Note:**

AWS KMS service is not related to the Key Management Service built into Hadoop (Hadoop KMS). The Hadoop KMS primarily focuses on managing keys for HDFS Transparent Encryption. Similarly, HDFS encryption is unrelated to S3 data encryption.

Enabling SSE-KMS

To enable SSE-KMS, the property `fs.s3a.server-side-encryption-algorithm` must be set to SSE-KMS in `core-site.xml`.

```
<property>
  <name>fs.s3a.server-side-encryption-algorithm</name>
  <value>SSE-KMS</value>
</property>
```

The ID of the specific key used to encrypt the data should also be set in the property `fs.s3a.server-side-encryption.key`:

```
<property>
<name>fs.s3a.server-side-encryption.key</name>
<value>arn:aws:kms:us-west-2:360379543683:key/071a86ff-8881-4ba0-9230-95af
6d01ca01</value>
</property>
```

If your account is set up with a default KMS key and `fs.s3a.server-side-encryption.key` is unset, the default key will be used.

Alternatively, organizations may define a default key in the Amazon KMS; if a default key is set, then it will be used whenever SSE-KMS encryption is chosen and the value of `fs.s3a.server-side-encryption.key` is empty.



Note: [AWS Key Management Service \(KMS\)](#) is pay-per-use, working with data encrypted via KMS keys incurs extra charges during data I/O.

To learn more, refer to [Protecting Data Using Server-Side Encryption with AWS KMS-Managed Keys \(SSE-KMS\)](#) in the AWS documentation.



Note: The AWS KMS key used must be in the same region as the S3 Bucket where the data is being encrypted.



Note: The KMS key specified is only used when writing new data, or when renaming objects. When reading an existing object, whichever KMS key was used to encrypt the data is reused to decrypt it.

IAM Role permissions for working with SSE-KMS

All IAM roles which need to read data encrypted with SSE-KMS must have the permissions to decrypt using the specific key the data was encrypted with: `kms:Decrypt`

All IAM roles which need to both read and write data need the encrypt and decrypt permissions (encrypt-only permission is not supported).

```
kms:Decrypt
kms:GenerateDatakey
```

If a role does not have the permissions to read data, it will fail with an `java.nio.AccessDeniedException`.



Note: The renaming files require the permission to decrypt the data, as it is decrypted and then re-encrypted as it is copied. See [AWS KMS API Permissions: Actions and Resources Reference](#) for more details on KMS permissions.

SSE-C: Server-Side Encryption with Customer-Provided Encryption Keys

In SSE-C, the client supplies the secret key needed to read and write data.

The same SSE-C key must be used on all clients reading or writing the data; this must be set client-side, in the hadoop configuration.

For hadoop applications to work reliably, SSE-C with a common key *must* be used exclusively within a bucket if it is to be used at all. This is the only way to ensure that path and directory listings do not fail with "Bad Request" errors.

Enabling SSE-C

To use SSE-C, the configuration option `fs.s3a.server-side-encryption-algorithm` must be set to SSE-C, and a base-64 encoding of the key placed in `fs.s3a.server-side-encryption.key`.

```
<property>
  <name>fs.s3a.server-side-encryption-algorithm</name>
  <value>SSE-C</value>
</property>

<property>
  <name>fs.s3a.server-side-encryption.key</name>
  <value>RG8gbm90IGV2ZXIgbG9nIHRoaXMga2V5IG9yIG90aGVyd2lzZSBzaGFyZSBpdA==</value>
</property>
```

This property can be set in a Hadoop JCEKS credential file, which is significantly more secure than embedding secrets in the XML configuration file.

Configuring Encryption for Specific Buckets

S3A's per-bucket configuration mechanism can be used to configure the encryption mechanism and credentials for specific buckets.

For example, to access the bucket called "production" using SSE-KMS with the key ID `arn:aws:kms:us-west-2:360379543683:key/071a86ff-8881-4ba0-9230-95af6d01ca01`, the settings are as follows:

```
<property>
  <name>fs.s3a.bucket.production.server-side-encryption-algorithm</name>
  <value>SSE-KMS</value>
</property>

<property>
  <name>fs.s3a.bucket.production.server-side-encryption.key</name>
  <value>arn:aws:kms:us-west-2:360379543683:key/071a86ff-8881-4ba0-9230-95af6d01ca01</value>
</property>
```

Encrypting an S3 Bucket with Amazon S3 Default Encryption

To guarantee that all data uploaded to a bucket is encrypted, it is possible to set a default encryption option for a bucket in the AWS management console.

For more information, see [Amazon S3 Default Encryption for S3 Buckets](#).

- This does not encrypt any data already stored in the bucket.

- S3A clients can still be configured to use a different encryption option if desired; this is the default value to use if no other policy was set.

A default encryption across a bucket offers significant benefits:

- It guarantees that all clients uploading data have encryption enabled.
- It guarantees that when a file is renamed, it will be re-encrypted, even if the client does not explicitly request encryption.
- If applied to an empty bucket, it guarantees that all future uploaded data in the bucket is encrypted.

We recommend selecting an encryption policy for a bucket when the bucket is created, and setting it in the bucket policy. This stops misconfigured clients from unintentionally uploading unencrypted data, or decrypting data when renaming files.

Performance Impact of Encryption

Server Side encryption slightly slows down performance when reading data from S3, both in the reading of data during the execution of a query, and in scanning the files prior to the actual scheduling of work.

Amazon [throttles reads and writes of S3-SSE data](#), which results in a significantly lower throughput than normal S3 IO requests. The default rate, 600 requests/minute, means that at most ten objects per second can be read or written using SSE-KMS per second — across an entire hadoop cluster (or the entire customer account). The default limits may be suitable during development — but in large scale production applications the limits may rapidly be reached. Contact Amazon to increase capacity.

Using S3Guard for Consistent S3 Metadata

S3Guard mitigates the issues related to S3's eventual consistency on listings by using a table on Amazon DynamoDB as a consistent metadata store. This guarantees a consistent view of data stored in S3.

In addition, S3Guard may improve query performance by reducing the number of times S3 needs to be contacted, — as DynamoDB is significantly faster.



Note: S3Guard should always be enabled on CDP in AWS as it is critical for guaranteeing the correctness of interactions with S3.

Introduction to S3Guard

Amazon S3 is an object store, not a filesystem. There are no directories, only objects. The S3A connector lets Hadoop, Hive and Spark applications see files in a directory tree, but really they are working on the objects underneath, by listing them and working on each one one-by-one.

Some of the operations which filesystems support are actually absent, with rename being the key one. The S3A connector mimics file or directory rename, by copying each file then deleting the original, which takes about 6-10 megabytes/second.

The S3 Object Store is "eventually consistent": when a file is deleted or overwritten it can take time for that change to propagate across all servers replicating the data. As a result, newly deleted files can still be visible, while queries of updated files can return the old version.

There is no specific time period by when the object store will be eventually consistent. The paper "[Benchmarking Eventual Consistency](#)" has shown it can vary by time of day, and be ten seconds or more — sometimes much more.

A critical problem is listing inconsistency: when a query is made of S3 to list all objects under a specific path, that listing can be out of date. This means that those operation on files under a "directory" mimicked by listing and acting on all objects underneath it are at risk of not seeing the complete list of files. Newly created files are at most risk.

This may affect the following operations on S3 data:

- When listing files, newly created objects may not be listed immediately and deleted objects may continue to be listed — which means that your input for data processing may be incorrect. In Hive, Spark, or MapReduce,

this could lead to erroneous results. In the worst case, it could potentially lead to data loss at the time of data movement.

- When renaming directories, the listing may be incomplete or out of date, so the rename operation loses files. This is very dangerous as MapReduce, Hive, Spark and Tez all rely on rename to commit the output of workers to the final output of the job. If data is lost, the output is incorrect —something which may not be immediately obvious.
- When deleting directories, the listing may be inconsistent, so not all objects are deleted. If another job writes data to the same directory path, the old data may still be present.
- During an ETL workflow, in a sequence of multiple jobs that form the workflow, the next job is launched soon after the previous job has been completed. Applications such as Oozie rely on marker files to trigger the subsequent workflows. Any delay in the visibility of these files can lead to delays in the subsequent workflows.
- During existence-guarded path operations, if a deleted file which has the same name as a target path appears in a listing, some actions may unexpectedly fail due to the target path being present — even though the file has already been deleted.

This eventually consistent behavior of S3 can cause seemingly unpredictable results from queries made against it, limiting the practical utility of the S3A connector for use cases where data gets modified.

S3Guard mitigates the issues related to S3's eventual consistency on listings by using a table on Amazon DynamoDB as a consistent metadata store. This guarantees a consistent view of data stored in S3. In addition, S3Guard may improve query performance by reducing the number of times S3 needs to be contacted, —as DynamoDB is significantly faster.

How S3Guard Works

S3Guard is a feature in the Hadoop S3A connector which uses Amazon's DynamoDB to cache information about created and deleted files, "The S3Guard Database".

When an application using the S3A Connector with S3Guard enabled manipulates objects in S3, such as creating, deleting or "renaming" them, the S3Guard database is updated. Newly created/copied files are added to the table, while deleted files have "tombstone markers" added to indicate that they have been deleted.

When a directory is listed on S3, the information from the S3Guard database is used to update the listing with this information: new files are added while those files with tombstone markers are not included in a listing.

As a result, the listing is up to date with all operations performed on the directory by all clients using S3Guard.

When a file is opened for reading, or any existence check made, the S3Guard database is checked first. If an entry is found in the database, that is used as the response —omitting all checks of S3 itself. This includes tombstone markers, which are used as evidence that a file does not exist. The caller is given the current state of the object (existence/nonexistence, size and type), without S3 being queried at all. This can be significantly faster than interacting with S3.

With this design, directory listings are kept consistent across a sequence of operations, even across multiple servers —indeed, across multiple Hadoop clusters.

What S3Guard Cannot Do

S3Guard only stores filenames, lengths, "etags" and optional version data in its DynamoDB tables. The contents of the files are still stored in S3. If a file is overwritten, S3's eventual consistency may mean that the old data is still present. S3 tries to detect this by using the following techniques:

- Storing the "etag" checksum of each file and detecting when the value is different from that in S3.
- In an S3 bucket with "versioning" enabled, the version is used to guarantee that the file loaded is the one matching the S3Guard record.

When a file is loaded, the S3A connector will make repeated attempts to load a file with the expected etag and version ID before concluding that it is not available — at which point the operation will fail.

S3Guard does not provide the "atomic directory rename" operation which many applications rely on to commit their intermediate work to the final destination of the job. This does not work in S3 where files are copied one-by-one in a slow process. If this operation is interrupted, the source and destination will be in an unknown state.

- For Spark applications, use an S3A committer.

- When copying files using `distcp`, avoid the `-atomic` option. All it will do is make the copy slower. Use the `-direct` operation for a direct upload, and be aware that a failure during the copy can leave the destination inconsistent.

Configuring S3Guard

You can enable S3Guard when configuring your CDP environment.

Configuring S3Guard on CDP Public Cloud

For information about configuring S3Guard on the CDP public cloud environment, see [Register an AWS environment](#) in the *Management Console* documentation.

Configuring S3Guard on CDP Private Cloud Base

To configure S3Guard on CDP Private Cloud Base, perform the following tasks:

1. [Preparing the S3 Bucket](#) on page 18
2. [Choosing a DynamoDB Table and IO Capacity](#) on page 18
3. [Creating DynamoDB Access Policy](#) on page 18
4. [Restricting Access to S3Guard Tables](#) on page 20
5. [Configuring S3Guard in Cloudera Manager](#) on page 21
6. [Create the S3Guard Table in DynamoDB](#) on page 22

Preparing the S3 Bucket

S3Guard can protect any read/write or read-only S3 bucket. To begin "guarding" a bucket, the first step is to create that bucket if it does not already exist.

Existing buckets can use S3Guard: after creation the data can be imported, though this is not necessary.

Except in when S3Guard is configured to operate in “authoritative mode” (which we do not recommend), clients using S3Guard can work with the same S3 bucket as applications not using S3Guard. Those clients not using S3Guard do not get the consistency, but their use can continue unchanged.

Choosing a DynamoDB Table and IO Capacity

When using DynamoDB, you must pay for the IO as well as the data storage: reads, writes and queries.

You can do this in two ways:

- **Provisioned Capacity** - You configure the DynamoDB table for a maximum number of reads and writes a second. You are then billed for this capacity for the life of the database, even when not using S3Guard. You are also limited to the maximum IO throughput of that provisioned capacity. This was originally the only billing mechanism for DynamoDB. Choosing an IO capacity was hard, as you needed to balance maximum throughput (usually Hive query planning) with the costs that would entail.
- **On demand** - When a table is created as an On demand table, you pay per IO operation. There is no monthly fee for pre-provisioned IO capacity, and your throughput is not limited to that prepaid capacity. You are, however, billed slightly more for each individual IO Operation.

For Cloudera applications, on demand billing mechanism is needed. When a bucket and its S3Guard table is unused, the sole dynamo DB costs are for storing the file metadata, not for any unused IO. Only when an application work with a S3Guard table, the caller is billed.

In CDP environments, S3Guard tables are always configured for on-demand billing. If you want to switch to provisioned IO capacity, you can configure using the [AWS DynamoDB console](#).


Creating DynamoDB Access Policy

In order to configure S3Guard, you must to provide read and write permissions for the DynamoDB table that S3Guard will create and use.


To do this, you must add a DynamoDB access policy to your [IAM role](#) using the following steps:

1. Log in to your AWS account and navigate to the Identity and Access Management (IAM) console.

- In the IAM console, select Roles from the left pane.
- Search for an IAM role that you want to update:



- Click on the role.
- In the Permissions tab, click Create Role Policy:



- Click Select next to the Policy Generator:



- Enter the following:

Table 2:

Step	Considerations
Effect	Allow
AWS Service	Amazon DynamoDB
Actions	All Actions

Step	Considerations
Amazon Resource Name (ARN)	*

Your configuration should look similar to:

8. Click Add Statement.
9. Click Next Step.
10. On the Review Policy page, review your new policy and then click Apply Policy:

Now the policy will be attached to your IAM role and your cluster will be able to talk to DynamoDB, including creating a table for S3 metadata when S3Guard is configured.

You must also [configure S3Guard in Cloudera Manager](#).

Restricting Access to S3Guard Tables

You must set permission to restrict access to S3Guard tables.

To restricting access to S3Guard tables, here are the permissions needed for simply using the table:

```
dynamodb:BatchGetItem
dynamodb:BatchWriteItem
dynamodb:DeleteItem
dynamodb:DescribeTable
dynamodb:GetItem
dynamodb:PutItem
dynamodb:Query
dynamodb:UpdateItem
```

For the `hadoop s3guard` table management commands, extra permissions are required:

```
dynamodb:CreateTable
dynamodb:DescribeLimits
dynamodb>DeleteTable
dynamodb:Scan
dynamodb:TagResource
dynamodb:UntagResource
dynamodb:UpdateTable
```

It is best to remove these rights, especially the `dynamodb:CreateTable` `dynamodb>DeleteTable` permissions from non-administrators.

Configuring S3Guard in Cloudera Manager

You must set permission to restrict access to S3Guard tables.

After you have created DynamoDB access policy, set the following S3Guard configuration parameters for each S3 bucket that you want to "guard".

1. In Cloudera Manager UI, navigate to Clusters > HDFS > Configuration > Advanced > Add property under Cluster-wide Advanced Configuration Snippet (Safety Valve) for `core-site.xml`.
2. Set the following configuration parameters for each bucket that you want to "guard". To configure S3Guard for a specific bucket, replace `fs.s3a.` with the `fs.s3a.bucket.<bucketname>`, where "bucketname" is the name of your bucket.
3. After you've added the configuration parameters, click Save to save the configuration changes.
4. Restart all affected components.

Table 3: S3Guard Configuration Parameters

Base Parameter	Default Value	Setting for S3Guard
<code>fs.s3a.metadatastore.impl</code>	<code>org.apache.hadoop.fs.s3a.s3guard.NullMetadataStore</code>	Set this to <code>org.apache.hadoop.fs.s3a.s3guard.S3GuardMetadataStore</code> .
<code>fs.s3a.s3guard.ddb.table.create</code>	<code>false</code>	Set this to "true" to automatically create a DynamoDB table for each bucket.
<code>fs.s3a.s3guard.ddb.table</code>	(Unset)	Enter a name for the table that will be created for each bucket. If you leave this blank while setting <code>fs.s3a.s3guard.ddb.table.create</code> to true, a default DynamoDB table will be created for each bucket, the respective S3 bucket name will be used as the DynamoDB table name.
<code>fs.s3a.s3guard.ddb.region</code>	(Unset)	Set this parameter to one of the regions listed in the Amazon documentation . The "region" will be used as this parameter value. If you leave this blank, the default region will be used.
<code>fs.s3a.s3guard.ddb.table.capacity.read</code>	500	Specify read capacity for DynamoDB. Monitor the DynamoDB workload on the AWS portal and adjust the read capacity to meet the workload requirements.
<code>fs.s3a.s3guard.ddb.table.capacity.write</code>	100	Specify write capacity for DynamoDB. Monitor the DynamoDB workload on the AWS portal and adjust the write capacity to meet the workload requirements.

Example

Adding the following custom properties will create a DynamoDB table called “guarded-table” in the “eu-west-1” region (where the “guarded-table” bucket is located). The configuration will be valid for a bucket called “guarded-table”, which means that “guarded-table” will only be used for storing metadata related to this bucket.

```
<property>
<name>fs.s3a.bucket.guarded-table.metadatastore.impl</name>
<value>org.apache.hadoop.fs.s3a.s3guard.DynamoDBMetadataStore</value>
</property>

<property>
<name>fs.s3a.bucket.guarded-table.s3guard.ddb.table</name>
<value>my-table</value>
</property>
<property>
<name>fs.s3a.bucket.guarded-table.s3guard.ddb.table.create</name>
<value>true</value>
</property>

<property>
<name>fs.s3a.bucket.guarded-table.s3guard.ddb.region</name>
<value>eu-west-1</value>
</property>
```

Create the S3Guard Table in DynamoDB

Unless the property `fs.s3a.bucket.test.s3guard.ddb.table.create` is set to enable the table to be automatically created, the table must be created on the command line using the `hadoop s3guard init` command.

```
hadoop s3guard init s3a://guarded-table/

2018-05-31 15:25:59,070 [main] INFO  s3guard.DynamoDBMetadataStore (Dynamo
DBMetadataStore.java:createTable(1025)) -
    Creating non-existent DynamoDB table guarded-table in region eu-
west-1
2018-05-31 15:26:11,759 [main] INFO  s3guard.S3GuardTool (S3GuardTool.java:
initMetadataStore(270)) -
    Metadata store DynamoDBMetadataStore{region=eu-west-1, tableNa
me=guarded-table} is initialized.
Metadata Store Diagnostics:
ARN=arn:aws:dynamodb:eu-west-1:980678866538:table/guarded-table
description=S3Guard metadata store in DynamoDB
name=guarded-table
read-capacity=500
region=eu-west-1
retryPolicy=ExponentialBackoffRetry(maxRetries=9, sleepTime=100 MILLISECO
NDS)
size=0
status=ACTIVE
table={AttributeDefinitions: [{AttributeName: child,AttributeType: S}, {At
tributeName: parent,AttributeType: S}],
    TableName: guarded-table,
    KeySchema: [{AttributeName: parent,KeyType: HASH}, {AttributeName: chi
ld,KeyType: RANGE}],
    TableStatus: ACTIVE,
    CreationDateTime: Thu May 31 15:25:59 BST 2018,
    ProvisionedThroughput: {NumberOfDecreasesToday: 0,ReadCapacityUnits: 5
00,WriteCapacityUnits: 100},
    TableSizeBytes: 0,
    ItemCount: 0,
    TableArn: arn:aws:dynamodb:eu-west-1:980678866538:table/guarded-table,
    TableId: fb50922a-90bf-4df2-a3c3-9f4aa6914d56,}
```

```
write-capacity=100
```

Once created, the table may be used immediately.

Monitoring and Maintaining S3Guard

The DynamoDB console on AWS allows you to monitor the workload on DynamoDB.

If you are not using auto scaling, the AWS console allows you to adjust the read/write capacities of the table. The command `hadoop s3guard set-capacity` can also be used to alter these values.

Disabling S3Guard and destroying a table

To disable S3Guard, you must delete the per-bucket `fs.s3a.metastore.impl` parameter or set it back to the default `org.apache.hadoop.fs.s3a.s3guard.NullMetadataStore`.

If you are not using a shared table, in DynamoDB console on AWS, delete the DynamoDB table to avoid incurring unnecessary costs.

Destroying S3Guard table

The command `hadoop s3guard destroy` can be used on the command line to destroy a table.

```
hadoop s3guard destroy s3a://guarded-table/
2018-05-31 15:35:39,075 [main] INFO  s3guard.S3GuardTool (S3GuardTool.java:
initMetadataStore(270)) -
    Metadata store DynamoDBMetadataStore{region=eu-west-1, tableName
=guarded-table} is initialized.
2018-05-31 15:35:39,077 [main] INFO  s3guard.DynamoDBMetadataStore (DynamoDB
MetadataStore.java:destroy(793)) -
    Deleting DynamoDB table guarded-table in region eu-west-1
Metadata store is deleted.
```

Destroying a table does not destroy the data in S3; it merely removes the summary data used by S3Guard to provide consistent listings. You can verify this by listing the bucket:

```
> hadoop fs -ls -R s3a://guarded-table/
-rw-rw-rw-  1 alice alice          0 2019-07-31 20:45 s3a://guarded-table/
example
```



Note:

Even though `hadoop fs` commands can print the owner and permissions of a file, these are not real attributes of the object, and generated for the benefit of applications which check them. The owner and group of a file or directory is always the user for whom the S3A Filesystem was instantiated. File permissions are always read and write; while directories are read, write and execute — irrespective of any underlying access permissions on the objects.

Pruning Old Data from S3Guard Tables

S3Guard keeps tombstone markers of deleted files. It is good to clean these regularly, just to keep costs down. This can be done with the `hadoop s3guard prune` command.

The command can be used to delete entries older than a certain number of days, minutes or hours.

```
> hadoop s3guard prune -days 3 s3a://guarded-table/
2019-07-31 21:27:37,264 [main] INFO  s3guard.S3GuardTool (S3GuardTool.java:in
itMetadataStore(321)) - Metadata store DynamoDBMetadataStore{region=eu-west-
2, tableName=guarded-table, tableArn=arn:aws:dynamodb:eu-west-2:980678866538
:table/guarded-table} is initialized.
2019-07-31 21:27:37,285 [main] INFO  s3guard.DynamoDBMetadataStore (Duratio
nInfo.java:<init>(72)) - Starting: Pruning DynamoDB Store
```

```
2019-07-31 21:27:37,332 [main] INFO s3guard.DynamoDBMetadataStore (DurationInfo.java:close(87)) - Pruning DynamoDB Store: duration 0:00.047s
2019-07-31 21:27:37,332 [main] INFO s3guard.DynamoDBMetadataStore (DynamoDBMetadataStore.java:innerPrune(1576)) - Finished pruning 366 items in batches of 25
```

Importing a Bucket into S3Guard

The `hadoop s3guard import` command can list and import a bucket's metadata into a S3Guard table. This is harmless if the contents are already imported.

```
hadoop s3guard import s3a://guarded-table/

2019-07-31 21:32:54,600 [main] INFO s3guard.S3GuardTool (S3GuardTool.java:initMetadataStore(321)) - Metadata store DynamoDBMetadataStore{region=eu-west-2, tableName=guarded-table, tableArn=arn:aws:dynamodb:eu-west-2:980678866538:table/guarded-table} is initialized.
Inserted 2 items into Metadata Store
```

You do not need to issue this command after creating a table; the data is added as listings of S3 paths find new entries. It merely saves by proactively building up the database.

Verifying that S3Guard is Enabled on a Bucket

When S3Guard is working, apart from some messages in the logs, there is no obvious clue that it is enabled. To verify that a bucket does have S3Guard enabled, use the command-line command `hadoop s3guard bucket-info`. This will print bucket information, and can be used to explicitly check that a bucket has s3guard enabled.

On a guarded bucket, it will list details about the bucket and the S3Guard Database on DynamoDB.

```
hadoop s3guard bucket-info s3a://example1/
Filesystem s3a://example1
Location: eu-west-1
Filesystem s3a://example1 is using S3Guard with store DynamoDBMetadataStore
{region=eu-west-1, tableName=example1, tableArn=arn:aws:dynamodb:eu-west-1:98067886600:table/example1}
Authoritative Metadata Store: fs.s3a.metadatastore.authoritative=false
Authoritative Path: fs.s3a.authoritative.path=
Metadata Store Diagnostics:
  ARN=arn:aws:dynamodb:eu-west-1:98067886600:table/example1
  billing-mode=per-request
  description=S3Guard metadata store in DynamoDB
  name=example1
  persist.authoritative.bit=true
  read-capacity=0
  region=eu-west-1
  retryPolicy=ExponentialBackoffRetry(maxRetries=9, sleepTime=250 MILLISECOND S)
  size=14431
  status=ACTIVE
  table={AttributeDefinitions: [{AttributeName: child,AttributeType: S}, {AttributeName: parent,AttributeType: S}],TableName: example1,KeySchema: [{AttributeName: parent,KeyType: HASH}, {AttributeName: child,KeyType: RANGE}],TableStatus: ACTIVE,CreationDateTime: Wed Jun 05 13:23:18 BST 2019,ProvisionedThroughput: {NumberOfDecreasesToday: 0,ReadCapacityUnits: 0,WriteCapacityUnits: 0},TableSizeBytes: 14431,ItemCount: 96,TableArn: arn:aws:dynamodb:eu-west-1:98067886600:table/example1,TableId: b4b1b660-9cbd-0000f10623,BillingModeSummary: {BillingMode: PAY_PER_REQUEST,LastUpdateToPayPerRequestDateTime: Wed Jun 05 13:32:07 BST 2019}},}
  write-capacity=0
The "magic" committer is supported

S3A Client
```



```

Signing Algorithm: fs.s3a.signing-algorithm=(unset)
Endpoint: fs.s3a.endpoint=s3-eu-west-1.amazonaws.com
Encryption: fs.s3a.server-side-encryption-algorithm=none
Input seek policy: fs.s3a.experimental.input.fadvise=normal
Change Detection Source: fs.s3a.change.detection.source=etag
Change Detection Mode: fs.s3a.change.detection.mode=server
Delegation token support is disabled

```

In this example the bucket is shown to be guarded by a table whose billing mode is "per-request".

Using the S3Guard CLI

The S3Guard CLI offers other maintenance commands. for information on how to use them, refer to [Apache documentation](#).

One useful command to use is `hadoop s3guard prune -tombstone`, which removes "tombstone markers" from the table. These are entries created when files are deleted, so as to identify recently deleted files which should be omitted from listings. After the S3 Store has become consistent with these deletions, the markers are no longer deleted.

```

> hadoop s3guard prune -tombstone -days 1 s3a://hwdev-steve-ireland-new/

2019-08-20 16:55:40,790 [main] INFO  s3guard.S3GuardTool - Metadata store
DynamoDBMetadataStore{region=eu-west-1, tableName=example1, tableArn=arn:aws
:dynamodb:eu-west-1:98067886600:table/example1} is initialized.
2019-08-20 16:55:40,810 [main] INFO  s3guard.DynamoDBMetadataStore - Startin
g: Pruning DynamoDB Store
2019-08-20 16:55:40,846 [main] INFO  s3guard.DynamoDBMetadataStore - Pruning
DynamoDB Store: duration 0:00.036s
2019-08-20 16:55:40,846 [main] INFO  s3guard.DynamoDBMetadataStore - Finis
hed pruning 0 items in batches of 25

```

S3Guard: Operational Issues

There are various issues and limitations that you must consider when working with S3Guard.

The following operational issues have been identified while testing S3Guard.

Third-party S3-compatible object stores

Third-party object stores which reimplement the AWS S3 protocol are usually "consistent". As such, there is no need to use S3Guard. Consult the object store's supplier as to its consistency model.

S3Guard Security Aspects

The DynamoDB table needs to be writeable by all users/services using S3Guard. If a single DynamoDB table is used to store metadata about multiple buckets, then clients with access to the table will be able to read the metadata about objects in any bucket to which their read access restricted via AWS permissions.

The standard S3 Bucket and Object Access permissions do not provide any restriction on accessing the S3Guard index data. As this is only the Hadoop file status data of object name, type, size and timestamp, the actual object data and any tags attached to the object are still protected by AWS permissions. However, directory and filenames will be visible.

Limitations of S3Guard

The key limitation of S3Guard is that it only provides consistent file and directory listings. It does not address update and delete consistency of the data. It is only consistent with respect to changes made by client applications using the S3A connector with S3Guard enabled and the same DynamoDB table. Changes which are made by other applications are only eventually consistent from the perspective of S3A clients.

S3Guard will track the etag of uploaded files, and, on a versioned S3 bucket, the S3 version ID of an uploaded file. These will be used when opening files, so as to detect and possibly react to changes.

Safely Writing to S3 Through the S3A Committers

The S3A committers are three different committers used to commit work directly to Mapreduce and Spark. The committers are enabled by default for Spark in CDP.

Introducing the S3A Committers

Amazon's S3 Object Store is not a filesystem: some expected behaviors of a filesystem are missing.

Some of the following aspects of S3 that are different from a filesystem are as follows:

- Directory listings are only eventually consistent.
- File overwrites and deletes are only eventually consistent: readers may get old data.
- There is no rename operation; it is mimicked in the S3A client by listing a directory and copying each file underneath, one-by-one.

Because directory rename is mimicked by listing and then copying files the eventual consistency of both listing and reading fails may result in incorrect data. And, because of the copying: it is slow.

S3Guard addresses the listing inconsistency problem. However, it does not address the update consistency or performance.

The normal means by which Hadoop MapReduce and Apache Spark commit work from multiple tasks is through renaming the output. Each task attempt writes to a private task attempt directory; when the task is given permission to commit by the MapReduce Application Master or Spark Driver, this task attempt directory is renamed into the job attempt directory. When the job is ready to commit, the output of all the tasks is merged into the final output directory, again by renaming files and directories.

This is fast and safe on HDFS and similar filesystems, and on object stores with rename operations, such as Azure WASB. On S3, it is unreliable without S3Guard, and even with S3Guard, the time to commit work to S3 is proportional to the amount of data written. An operation which may work well during development can turn out to be unusable in production.

To address this the S3A committers were developed. They allow the output of MapReduce and Spark jobs to be written directly to S3, with a time to commit the job independent of the amount of data created.

What Are the S3A Committers?

The S3A committers are three different committers which can be used to commit work directly to Map-reduce and Spark. They differ in how they deal with conflict and how they upload data to the destination bucket—but underneath they all share much of the same code.

They rely on a specific S3 feature: multipart upload of large files.

When writing a large object to S3, S3A and other S3 clients use a mechanism called “Multipart Upload”.

The caller initiates a “multipart upload request”, listing the destination path and receiving an upload ID to use in the upload operations.

The caller then uploads the data in a series of HTTP POST requests, closing with a final POST listing the blocks uploaded.

The uploaded data is not visible until that final POST request is made, at which point it is published in a single atomic operation.

This mechanism is always used by S3A whenever it writes large files; the size of each part is set to the value of `fs.s3a.multipart.size`

The S3A Committers use the same multipart upload process, but convert it into a mechanism for committing the work of tasks because of a special feature of the mechanism: The final POST request does not need to be issued by the same process or host which uploaded the data.

The output of each worker task can be uploaded to S3 as a multipart upload, but without issuing the final POST request to complete the upload. Instead, all the information needed to issue that request is saved to a cluster-wide filesystem (HDFS or potentially S3 itself)

When a job is committed, this information is loaded, and the upload completed. If a task is aborted or fails: the upload is not completed, so the output does not become visible. If the entire job fails, none of its output becomes visible.

For further reading, see:

- [HADOOP-13786](#): Add S3A committers for zero-rename commits to S3 endpoints.
- [S3A Committers: Architecture and Implementation](#).
- [A Zero-Rename Committer](#): Object-storage as a Destination for Apache Hadoop and Spark.

The Three Committers

The three different S3A committers are directory committer, partitioned committer, magic committer.

- **Directory Committer**: Buffers working data to the local disk, uses HDFS to propagate commit information from tasks to job committer, and manages conflict across the entire destination directory tree.
- **Partitioned Committer**: Identical to the Directory committer except that conflict is managed on a partition-by-partition basis. This allows it to be used for in-place updates of existing datasets. It is only suitable for use with Spark.
- **Magic Committer**: Data is written directly to S3, but “magically” re-targeted at the final destination. Conflict is managed across the directory tree. It requires a consistent S3 object store, which means S3Guard is a mandatory pre-requisite.

We currently recommend use of the “Directory” committer: it is the simplest of the set, and by using HDFS to propagate data from workers to the job committer, does not directly require S3Guard – this makes it easier to set up.

The rest of the documentation only covers the Directory Committer: to explore the other options, consult the Apache documentation.

Configuring Directories for Intermediate Data

In addition to `fs.s3a.committer.name`, two other `core-site.xml` configuration options are used to control where intermediate is stored.

A location in the local filesystem for buffering data

```
<property>
  <name>fs.s3a.buffer.dir</name>
  <value>${hadoop.tmp.dir}/s3a</value>
  <description>Comma separated list of directories that will be used to buffer file uploads to.</description>
</property>
```

These directories will store the output created by all active tasks until each task is committed; the more worker processes/spark worker threads a host can support, the more disk space will be needed. Multiple disks can be listed to help spread the load, and recover from disk failure.

A location in the cluster's HDFS filesystem to share summary data about pending uploads.

```
<property>
  <name>fs.s3a.committer.staging.tmp.path</name>
  <value>tmp/staging</value>
</property>
```

These files are generally quite small: a few kilobytes per task.

Using the Directory Committer in MapReduce

Once the property `fs.s3a.committer.name` is set, Hadoop MapReduce jobs writing to paths using the `s3a://` schema will automatically switch to the new committers.

Jobs using any other filesystem as a destination will still use the normal file committer.

Verifying That an S3A Committer Was Used

When working correctly, the only sign the new committers are in use is that it should be faster to use S3 as a destination of work.

There is a straightforward way to determine if a new committer was used: examine the `_SUCCESS` file created in the destination directory of a query. With the original file committer, this is a zero-byte file. The new S3A committers all write a JSON file describing the committer used, the files created and various diagnostics information.

Listing this file is enough to show whether an S3A committer was used:

```
hadoop fs -ls s3a://guarded-bucket/datasets/orc/_SUCCESS
```

If this file is of size 0, then no S3A committer was used. If the file length is greater than zero, then an S3A committer was used.

To see more details about the job commit operation, the file's contents can be printed.

```
hadoop fs -cat s3a://guarded-bucket/datasets/orc/_SUCCESS
```

Cleaning up after failed jobs

The S3A committers upload data in the tasks, completing the uploads when the job is committed.

About this task

Amazon AWS still bill you for all data held in this “pending” state. The `hadoop s3guard uploads` command can be used to list and cancel such uploads. However, it is simplest to automate cleanup with a bucket lifecycle rule.

Procedure

1. Go to the AWS S3 console: <https://s3.console.aws.amazon.com/>.
2. Find the bucket you are using as a destination of work.
3. Select the Management tab.
4. Select Add a new lifecycle rule.
5. Create a rule “cleanup uploads” with no filter, and without any “transitions”.
Configure an “Expiration” action of Clean up incomplete multipart uploads.
6. Select a time limit for outstanding uploads, such as 1 Day.
7. Review and confirm the lifecycle rule

You need to select a limit of how long uploads can be outstanding. For Hadoop applications, this is the maximum time that either an application can write to the same file and the maximum time which a job may take. If the timeout is shorter than either of these, then programs are likely to fail.

Once the rule is set, the cleanup is automatic.

Using the S3Guard Command to List and Delete Uploads

The `hadoop s3guard uploads` command can also be used to list all outstanding uploads under a path, and delete them.

```
hadoop s3guard uploads s3a://guarded-bucket/
tests3ascale/scale/hugefile nB3gctgP34ZSpzJ5_o2AVb7kKRiicXfbkBqIfLA0y.IH7Ci
mH100VUzohRCj3QfFstoQIdcge478ZidXu764yN0vuGI1j5kcOV3rDhsrc.RBZ5skZ93jVCN9g2c
21QgB
```

```
Total 1 uploads found.
```

All outstanding uploads can be aborted, or those older than a certain age.

```
hadoop s3guard uploads -abort -days 1 -force s3a://guarded-bucket/
Deleting: tests3ascale/scale/hugefile nB3gctgP34ZSpzJ5_o2AVb7kKRiicXfbkBq
IfLA0y.IH7CimH100VUzohRCj3QfFstoQIdcge478ZidXu764yN0vuGI1j5kc0V3rDhsrc.RBZ5s
kZ93jVCN9g2c21QgB
2018-06-28 20:58:18,504 [main] INFO s3a.S3AFileSystem (S3AFileSystem.java:
abortMultipartUpload(3266)) - Aborting multipart upload nB3gctgP34ZSpzJ5_o2A
Vb7kKRiicXfbkBqIfLA0y.IH7CimH100VUzohRCj3QfFstoQIdcge478ZidXu764yN0vuGI1j5kc
0V3rDhsrc.RBZ5skZ93jVCN9g2c21QgB to tests3ascale/scale/hugefile
Total 1 uploads deleted.
```

While bucket lifecycle is the best way to guarantee that all outstanding uploads are deleted; this command line tool is useful to verify that such cleanup is taking place, or explicitly clean up after a failure.

Advanced Committer Configuration

The Apache documentation covers the full set of configuration options for the committers.

Enabling Speculative Execution

The S3A committers all support speculative execution.

For MapReduce, enable the following properties in the job:

```
mapreduce.map.speculative true
mapreduce.reduce.speculative true
```

For Spark, set the following configuration option:

```
spark.speculation true
```

Using Unique Filenames to Avoid File Update Inconsistency

When updating existing datasets, if a new file overwrites an existing file of the same name, S3's eventual consistency on file updates means that the old data may still be returned.

To avoid this, unique filenames should be used when creating files. The property `fs.s3a.committer.staging.unique-file-names` enables this.

```
<property>
  <name>fs.s3a.committer.staging.unique-filename</name>
  <value>true</value>
</property>
```

It is set to true by default; you only need to disable it if you explicitly want newly created files to have the same name as any predecessors.

Speeding up Job Commits by Increasing the Number of Threads

When an individual job writes many files to S3, the time to commit the job can increase.

It can be speeded up by increasing the value of `fs.s3a.committer.threads`. However, the value of `fs.s3a.connection.maximum` must be at least this size otherwise the limit on the number of parallel uploads is still limited.

```
<property>
  <name>fs.s3a.committer.threads</name>
  <value>8</value>
</property>
<property>
  <name>fs.s3a.connection.maximum</name>
  <value>15</value>
```

```
</property>
```

Securing the S3A Committers

There are a few security considerations when using the S3A committers.

S3 Bucket Permissions

To use an S3A committer, the account/role must have the same AWS permissions as needed to write to the destination bucket.

The multipart upload list/abort operations may be a new addition to the permissions for the active role.

When using S3Guard, the account/role must also have full read/write/delete permissions for the DynamoDB table used.

Local Filesystem Security

All the committers use the directories listed in `fs.s3a.buffer.dir` to store staged/buffered output before uploading it to S3.

To ensure that other processes running on the same host do not have access to this data, unique paths should be used per-account.

This requirement holds for all applications working with S3 through the S3A connector.

HDFS Security

The directory and partitioned committers use HDFS to propagate commit information between workers and the job committer.

These intermediate files are saved into a job-specific directory under the path `${fs.s3a.committer.staging.tmp.path}/${user}` where `${user}` is the name of the user running the job.

The default value of `fs.s3a.committer.staging.tmp.path` is `tmp/staging`, Which will be converted at run time to a path under the current user's home directory, essentially `/user/${user}/tmp/staging/${user}/`.

Provided the user's home directory has access restricted to trusted accounts, this intermediate data will be secure.

If the property `fs.s3a.committer.staging.tmp.path` is changed to a different location, then this path will need to be secured to protect pending jobs from tampering.



Note: This intermediate data does not contain the output, merely the listings of all pending files and the MD5 checksums of each block.

The S3A Committers and Third-Party Object Stores

The S3A committers will work with any object store which implements the AWS S3 protocols.

The directory committer requires a consistent cluster filesystem to propagate commit information from the worker processes to the job committer. This is normally done in HDFS.

If the third-party object store is consistent, then it may also be used as the cluster filesystem. Set `fs.s3a.committer.staging.tmp.path` to a chosen path in the store.

Limitations of the S3A Committers

There are limitations of the S3A committers associated with custom file output formats, MapReduce API output format, and non-availability of Hive support.

Custom file output formats and their committers

Output formats which implement their own committers do not automatically switch to the new committers. If such a custom committer relies on renaming files to commit output, then it will depend on S3Guard for a consistent view of the object store, and take time to commit output proportional to the amount of data and the number of files.

To determine if this is the case, find the subclass of `org.apache.hadoop.mapreduce.lib.output.FileOutputFormat` which implements the custom format, to see if it subclasses the `getOutputCommitter()` to return its own committer, or has a custom subclass of `org.apache.hadoop.mapreduce.lib.output.FileOutputCommitter`.

It may be possible to migrate such a committer to support store-specific committers, as was done for Apache Parquet support in Spark. Here a subclass of Parquet's `ParquetOutputCommitter` was implemented to delegates all operations to the real committer.

MapReduce V1 API Output Format and Committers

Only the MapReduce V2 APIs under `org.apache.hadoop.mapreduce` support the new committer binding mechanism. The V1 APIs under the `org.apache.hadoop.mapred` package only bind to the file committer and subclasses. The v1 APIs date from Hadoop 1.0 and should be considered obsolete. Please migrate to the v2 APIs, not just for the new committers, but because the V2 APIs are still being actively developed and maintained.

No Hive Support

There is currently no Hive support for the S3A committers. To safely use S3 as a destination of Hive work, you must use `S3Guard`.

Troubleshooting the S3A Committers

The [Apache documentation](#) contains information about troubleshooting the committers.

The primary issue which surfaces is actually programs not switching to the new committers. There are three common reasons for this.

- The configuration settings to switch to the new committer are not being picked up. This is particularly common in Spark, which is harder to set up.
- The program is using the older V1 MapReduce APIs. Fix: switch to the V2 API.
- The output format the program uses is explicitly creating its own committer. This can only be fixed by modifying the program.

To help debug Spark's configuration, there is an option which can be set to forcibly fail the spark query if the path output committer is used. However, the file committer is being returned.

```
spark.hadoop.pathoutputcommit.reject.fileoutput true
```

There is also the blunt-instrument approach of causing the original output committer to crash with an invalid configuration.

```
spark.hadoop.mapreduce.fileoutputcommitter.algorithm.version 3
```

This (invalid) option ensures that if the original file committer is used, it will raise an exception.

To enable low-level logging of the committers, set the log-level of the package `org.apache.hadoop.fs.s3a.commit` to `DEBUG`. With `Log4J`, this can be one in `log4j.properties`:

```
log4j.logger.org.apache.hadoop.fs.s3a.commit=DEBUG
```

Security Model and Operations on S3

The security and permissions model of Amazon S3 is very different from this of a UNIX-style filesystem: on Amazon S3, operations which query or manipulate permissions are generally unsupported. Operations to which this applies include: `chgrp`, `chmod`, `chown`, `getfacl`, and `setfacl`. The related attribute commands `getfattr` and `setfattr` are also unavailable.

In addition, operations which try to preserve permissions (for example `fs -put -p`) do not preserve permissions.

Although these operations are unsupported, filesystem commands which list permission and user/group details usually simulate these details. As a consequence, when interacting with read-only object stores, the permissions found in “list” and “stat” commands may indicate that the user has write access — when they do not.

Amazon S3 has a permissions model of its own. This model can be manipulated through store-specific tooling. Be aware that some of the permissions which can be set — such as write-only paths, or various permissions on the root path — may be incompatible with the S3A client. It expects full read and write access to the entire bucket with trying to write data, and may fail if it does not have these permissions.

As an example of how permissions are simulated, here is a listing of Amazon's public, read-only bucket of Landsat images:

```
$ hadoop fs -ls s3a://landsat-pds/
Found 10 items
drwxrwxrwx - mapred 0 2016-09-26 12:16 s3a://landsat-pds/L8
-rw-rw-rw- 1 mapred 23764 2015-01-28 18:13 s3a://landsat-pds/index.html
drwxrwxrwx - mapred 0 2016-09-26 12:16 s3a://landsat-pds/landsat-pds_stats
-rw-rw-rw- 1 mapred 105 2016-08-19 18:12 s3a://landsat-pds/robots.txt
-rw-rw-rw- 1 mapred 38 2016-09-26 12:16 s3a://landsat-pds/run_info.json
drwxrwxrwx - mapred 0 2016-09-26 12:16 s3a://landsat-pds/runs
-rw-rw-rw- 1 mapred 27458808 2016-09-26 12:16 s3a://landsat-pds/scene_list.
gz
drwxrwxrwx - mapred 0 2016-09-26 12:16 s3a://landsat-pds/tarq
drwxrwxrwx - mapred 0 2016-09-26 12:16 s3a://landsat-pds/tarq_corrupt
drwxrwxrwx - mapred 0 2016-09-26 12:16 s3a://landsat-pds/test
```

The following is evident from the examples:

- All files are listed as having full read/write permissions.
- All directories appear to have full rwx permissions.
- The replication count of all files is "1".
- The owner of all files and directories is declared to be the current user (mapred).
- The timestamp of all directories is actually that of the time the `-ls` operation was executed. This is because these directories are not actual objects in the store; they are simulated directories based on the existence of objects under their paths.

When an attempt is made to delete one of the files, the operation fails — despite the permissions shown by the `ls` command:

```
$ hadoop fs -rm s3a://landsat-pds/scene_list.gz
rm: s3a://landsat-pds/scene_list.gz: delete on s3a://landsat-pds/scene_list.
gz:
com.amazonaws.services.s3.model.AmazonS3Exception: Access Denied (Service: A
mazon S3;
Status Code: 403; Error Code: AccessDenied; Request ID: 1EF98D5957BCAB3D),
S3 Extended Request ID: wi3ve0XFuFqWBUCJgV3Z+NQVj9gwgZVdXlPU4KBbYMSw/gA+hyh
RXcaQ+Pog0sDgHh31HlTCebQ=
```

This demonstrates that the listed permissions cannot be taken as evidence of write access. Only object manipulation can determine this.

S3A and Checksums (Advanced Feature)

The S3A connector can be configured to export the HTTP etag of an object as a checksum, by setting the option `fs.s3a.etag.checksum.enabled` to `true`. When unset (the default), S3A objects have no checksum.

```
$ hadoop fs -touchz s3a://hwdev-bucket/src/something.txt
$ hadoop fs -checksum s3a://hwdev-bucket/src/something.txt
```



```
s3a://hwdev-bucket/src/something.txt NONE
```

Once set, S3A objects have a checksum which is created on upload.

```
$ hadoop fs -Dfs.s3a.etag.checksum.enabled=true -checksum s3a://hwdev-bucket
/src/something.txt
s3a://hwdev-bucket/src/something.txt etag 6434316438636439386630306232303
465393830303939386563663834323765
```

This checksum is not compatible with that of HDFS, so cannot be used to compare file versions when using the `-update` option on `DistCp` between S3 and HDFS. More specifically, unless `-skipcrccheck` is set, the `DistCP` operation will fail with a checksum mismatch. However, it can be used for incremental updates within and across S3A buckets.

```
$ hadoop distcp -Dfs.s3a.etag.checksum.enabled=true --update s3a://hwdev-buc
ket/src s3a://hwdev-bucket/dest
$ hadoop fs -Dfs.s3a.etag.checksum.enabled=true -checksum s3a://hwdev-bucke
t/dest/something.txt
s3a://hwdev-bucket/src/something.txt etag 643431643863643938663030623230346
5393830303939386563663834323765
```

As the checksums match small files created as a single block, incremental updates will not copy unchanged files. For large files uploaded using multiple blocks, the checksum values may differ in which case the source file will be copied again.

A List of S3A Configuration Properties

All S3A client options are configured with options with the prefix `fs.s3a`.

For information about the S3A configuration properties, see [General S3A client configuration](#).

Working with versioned S3 buckets

AWS S3 supports "Versioning" in buckets, where the bucket is configured to save older versions of objects. When an object is overwritten (or even deleted), the old version can be accessed when a request is made for the object using the original version ID.

For more information, see [Using Versioning](#).

The S3A connector supports versioning in the following ways:

- S3Guard will record the `versionId` of new files written into the store. It can then use that value when opening a file, so that it can guarantee that the specific version listed in the S3Guard table is opened. This can compensate for eventual consistency of overwritten data—even if the old version is initially found when opening the file, the S3A connector can retry until the new version is found.
- When a file is opened for reading, the version ID of that file is recorded, and then for the duration of the file read (seconds, minutes, hours...) only that version of the data is read. Even if the file is overwritten, the single ongoing file read will always read the original data.
- When a file is copied (as in a rename operation), the version ID is used to guarantee that even if the source file is overwritten, the copied file will be the original version.
- It can be used as an alternative to moving deleted files to a trash location: simply delete the files and then recover them later. Note: The S3A connector does not provide a recovery tool.

The following are some issues you must be aware of when using versioning:

- Too many S3 Tombstone markers from deleted objects will slow down directory listings, and can result in clients being throttled (<https://docs.aws.amazon.com/AmazonS3/latest/dev/troubleshooting.html#troubleshooting-by-symptom-increase-503-reponses>)

- Old versions of files are still billed for.

To keep costs down and minimize performance problems, we recommend having a lifecycle rule on the bucket which deletes older versions of files after a number of days. This can be done from the Management tab of the AWS S3 console.

Here is an example policy which deletes all versions of objects which were overwritten more than a week previously, while also cleaning up tombstone markers and incomplete file uploads:

Working with Third-party S3-compatible Object Stores

The S3A Connector can work with third-party object stores; some vendors test the connector against their stores — and even actively collaborate in developing the connector in the open source community.

Option	Change to
fs.s3a.endpoint	(the hostname of the S3 Store)
fs.s3a.path.style.access	true

Option	Change to
fs.s3a.signing-algorithm	If the default signing mechanism is rejected, another mechanism may work from: "QueryStringSignerType", "S3SignerType", "AWS3SignerType", "AWS4SignerType", "AWS4UnsignedPayloadSignerType" and "NoOpSignerType".
fs.s3a.connection.ssl.enabled	Set to "false" if HTTP is used instead of HTTPS
fs.s3a.multipartdelete.enable	Set to "false" if bulk delete operations are not supported.
fs.s3a.list.version	Set to "1" if the list directories with the default "2" option fails with an error.

Third-party object stores are generally consistent; there is no need for S3Guard. The S3A Committers will still offer better performance, and should be used for MapReduce and Spark.

Encryption may or may not be supported: consult the documentation.

Security permissions are likely to be implemented differently from the IAM role mode —again, consult the documentation to see what is available.

Improving Performance for S3A

You can consider various options for improving performance when working with data stored in Amazon S3.

The bandwidth between the CDP cluster and Amazon S3 is the upper limit to how fast data can be copied into S3. The further the CDP cluster is from the Amazon S3 installation, or the narrower the network connection is, the longer the operation will take. Even a CDP cluster deployed within Amazon's own infrastructure may encounter network delays from throttled VM network connections.

Network bandwidth limits notwithstanding, there are some options which can be used to tune the performance of an upload:

- [Working with S3 buckets in the same AWS region](#) on page 35
- [Configuring and tuning S3A block upload](#) on page 35

Working with S3 buckets in the same AWS region

A foundational step to getting good performance is working with buckets close to the Hadoop cluster, where "close" is measured in network terms.

Maximum performance is achieved from working with S3 buckets in the same AWS region as the cluster. For example, if your cluster is in North Virginia ("US East"), you will achieve best performance if your S3 bucket is in the same region.

In addition to improving performance, working with local buckets ensures that no bills are incurred for reading from the bucket.

Configuring and tuning S3A block upload

Because of the nature of the S3 object store, data written to an S3A OutputStream is not written incrementally — instead, by default, it is buffered to disk until the stream is closed in its `close()` method. This can make output slow because the execution time for `OutputStream.close()` is proportional to the amount of data buffered and inversely proportional to the bandwidth between the host to S3; that is $O(\text{data}/\text{bandwidth})$.

Other work in the same process, server, or network at the time of upload may increase the upload time.

In summary, the further the process is from the S3 store, or the smaller the EC2 VM is, the longer it will take complete the work. This can create problems in application code:

- Code often assumes that the `close()` call is fast; the delays can create bottlenecks in operations.
- Very slow uploads sometimes cause applications to time out - generally, threads blocking during the upload stop reporting progress, triggering timeouts.

- Streaming very large amounts of data may consume all disk space before the upload begins.

Tuning S3A Uploads

When data is written to S3, it is buffered locally and then uploaded in multi-Megabyte blocks, with the final upload taking place as the file is closed.

The following major configuration options are available for the S3A block upload options. These are used whenever data is written to S3.

Parameter	Default Value	Description
fs.s3a.multipart.size	100M	Defines the size (in bytes) of the blocks into which the upload or copy operations will be split up. A suffix from the set {K,M,G,T,P} may be used to scale the numeric value.
fs.s3a.fast.upload.active.blocks	8	Defines the maximum number of blocks a single output stream can have active uploading, or queued to the central FileSystem instance's pool of queued operations. This stops a single stream overloading the shared thread pool.
fs.s3a.buffer.dir	Empty value	A comma separated list of temporary directories use for storing blocks of data prior to their being uploaded to S3. When unset (by default), the Hadoop temporary directory <code>hadoop.tmp.dir</code> is used.
fs.s3a.fast.upload.buffer	disk	The <code>fs.s3a.fast.upload.buffer</code> determines the buffering mechanism to use when uploading data. Allowed values are: disk, array, bytebuffer: • (default) "disk" will use the directories listed in <code>fs.s3a.buffer.dir</code> as the location(s) to save data prior to being uploaded. • "array" uses arrays in the JVM heap. • "bytebuffer" uses off-heap memory within the JVM. Both "array" and "bytebuffer" will consume memory in a single stream up to the number of blocks set by: <code>fs.s3a.multipart.size * fs.s3a.fast.upload.active.blocks</code>. If using either of these mechanisms, keep this value low. The total number of threads performing work across all threads is set by <code>fs.s3a.threads.max</code>, with <code>fs.s3a.max.total.tasks</code> values setting the number of queued work items.

Note that:

- If the amount of data written to a stream is below that set in `fs.s3a.multipart.size`, the upload takes place after the application has written all its data.
- The maximum size of a single file in S3 is one thousand blocks, which, for uploads means $10000 * fs.s3a.multipart.size$. Too A small value of `fs.s3a.multipart.size` can limit the maximum size of files.
- Incremental writes are not visible; the object can only be listed or read when the multipart operation completes in the `close()` call, which will block until the upload is completed.

Buffering uploads to disk or RAMs

This is the default buffer mechanism. The amount of data which can be buffered is limited by the amount of available disk space.

When `fs.s3a.fast.upload.buffer` is set to "disk", all data is buffered to local hard disks prior to upload. This minimizes the amount of memory consumed, and so eliminates heap size as the limiting factor in queued uploads.

Buffering uploads in Byte Buffers

When `fs.s3a.fast.upload.buffer` is set to "bytebuffer", all data is buffered in "direct" ByteBuffers prior to upload. This may be faster than buffering to disk in cases such as when disk space is small there may not be much disk space to buffer with (for example, when using "tiny" EC2 VMs).

The ByteBuffers are created in the memory of the JVM, but not in the Java Heap itself. The amount of data which can be buffered is limited by the Java runtime, the operating system, and, for YARN applications, the amount of memory requested for each container.

The slower the upload bandwidth to S3, the greater the risk of running out of memory — and so the more care is needed in tuning the upload thread settings to reduce the maximum amount of data which can be buffered awaiting upload.

Buffering Uploads with Array Buffers

When `fs.s3a.fast.upload.buffer` is set to "array", all data is buffered in byte arrays in the JVM's heap prior to upload. This may be faster than buffering to disk.

The amount of data which can be buffered is limited by the available size of the JVM heap. The slower the write bandwidth to S3, the greater the risk of heap overflows. This risk can be mitigated by tuning the upload thread settings.

Thread Tuning for S3A Data Upload

Both the array and bytebuffer buffer mechanisms can consume very large amounts of memory, on-heap or off-heap respectively. The disk buffer mechanism does not use much memory up, but it consumes hard disk capacity.

If there are many output streams being written to in a single process, the amount of memory or disk used is the multiple of all streams' active memory and disk use.

You may need to perform careful tuning to reduce the risk of running out memory, especially if the data is buffered in memory. There are a number parameters which can be tuned:

Parameter	Default Value	Description
<code>fs.s3a.fast.upload.active.blocks</code>	4	Maximum number of blocks a single output stream can have active (uploading, or queued to the central FileSystem instance's pool of queued operations). This stops a single stream overloading the shared thread pool.
<code>fs.s3a.threads.max</code>	10	The total number of threads available in the filesystem for data uploads or any other queued filesystem operation.
<code>fs.s3a.max.total.tasks</code>	5	The number of operations which can be queued for execution
<code>fs.s3a.threads.KeepAliveTime</code>	60	The number of seconds a thread can be idle before being terminated.

When the maximum allowed number of active blocks of a single stream is reached, no more blocks can be uploaded from that stream until one or more of those active block uploads completes. That is, a `write()` call which would trigger an upload of a now full datablock will instead block until there is capacity in the queue.

Consider the following:

- As the pool of threads set in `fs.s3a.threads.max` is shared (and intended to be used across all threads), a larger number here can allow for more parallel operations. However, as uploads require network bandwidth, adding more threads does not guarantee speedup.

- The extra queue of tasks for the thread pool (`fs.s3a.max.total.tasks`) covers all ongoing background S3A operations.
- When using memory buffering, a small value of `fs.s3a.fast.upload.active.blocks` limits the amount of memory which can be consumed per stream.
- When using disk buffering, a larger value of `fs.s3a.fast.upload.active.blocks` does not consume much memory. But it may result in a large number of blocks to compete with other filesystem operations.

We recommend a low value of `fs.s3a.fast.upload.active.blocks` — enough to start background upload without overloading other parts of the system. Then experiment to see if higher values deliver more throughput — especially from VMs running on EC2.

Optimizing S3A read performance for different file types

The S3A filesystem client supports the notion of input policies, similar to that of the POSIX `fcntl` API call. This tunes the behavior of the S3A client to optimize HTTP GET requests for reading different filetypes. To optimize HTTP GET requests, you can take advantage of the S3A input policy option `fs.s3a.experimental.input.fadvise`.

Policy	Description
"normal"	This starts off as "sequential": it asks for the whole file. As soon as the application tries to seek backwards in the file it switches into "random" IO mode. This is not quite as efficient for Random IO as the "random" mode, because that first read may have to be aborted. However, because it is adaptive, it is the best choice if you do not know the data formats which will be read.
"sequential" (default)	Read through the file, possibly with some short forward seeks. The whole document is requested in a single HTTP request; forward seeks within the readahead range are supported by skipping over the intermediate data. This leads to maximum read throughput, but with very expensive backward seeks.
"random"	Optimized for random IO, specifically the Hadoop <code>PositionedReadable</code> operations — though <code>seek(offset); read(byte_buffer)</code> also benefits. Rather than ask for the whole file, the range of the HTTP request is set to that of the length of data desired in the <code>read</code> operation - rounded up to the readahead value set in <code>setReadahead()</code> if necessary. By reducing the cost of closing existing HTTP requests, this is highly efficient for file IO accessing a binary file through a series of <code>PositionedReadable.read()</code> and <code>PositionedReadable.readFully()</code> calls. Sequential reading of a file is expensive, as now many HTTP requests must be made to read through the file.

For operations simply reading through a file (copying, DistCp, reading gzip or other compressed formats, parsing .csv files, and so on) the sequential policy is appropriate. This is the default, so you do not need to configure it.

For the specific case of high-performance random access IO (for example, accessing ORC files), you may consider using the random policy in the following circumstances:

- Data is read using the `PositionedReadable` API.
- There are long distance (many MB) forward seeks.
- Backward seeks are as likely as forward seeks.
- There is little or no use of single character `read()` calls or small `read(buffer)` calls.
- Applications are running close to the Amazon S3 data store; that is, the EC2 VMs on which the applications run are in the same region as the Amazon S3 bucket.

You must set the desired fadvise policy in the configuration option `fs.s3a.experimental.input.fadvise` when the filesystem instance is created. It can only be set on a per-filesystem basis, not on a per-file-read basis. You can set it in `core-site.xml`:

```
<property>
  <name>fs.s3a.experimental.input.fadvise</name>
  <value>random</value>
</property>
```

Or, you can set it in the `spark-defaults.conf` configuration of Spark:

```
spark.hadoop.fs.s3a.experimental.input.fadvise random
```

Be aware that this random access performance comes at the expense of sequential IO — which includes reading files compressed with gzip.

S3 Performance Checklist

There are various types of checklists that you can use to ensure optimal performance when working with data in S3.

Checklist for Data

- [] Amazon S3 bucket is in same region as the EC2-hosted cluster.
- [] The directory layout is "shallow". For directory listing performance, the directory layout prefers "shallow" directory trees with many files over deep directory trees with only a few files per directory.
- [] The "pseudo" block size set in `fs.s3a.block.size` is appropriate for the work to be performed on the data.
- [] Copy to HDFS any data that needs to be repeatedly read to HDFS.

Checklist for Cluster Configurations

- [] Set `yarn.scheduler.capacity.node-locality-delay` to 0 to improve container launch times.

Checklist for Code

- [] Application does not make `rename()` calls. Where it does, it does not assume the operation is immediate.
- [] Application does not assume that `delete()` is near-instantaneous.
- [] Application uses `FileSystem.listFiles(path, recursive=true)` to list a directory tree.
- [] Application prefers forward seeks through files, rather than full random IO.
- [] If making "random" IO through `seek()` and `read()` sequences or and Hadoop's `PositionedReadable` API, `fs.s3a.experimental.input.fadvise` is set to `random`.

Troubleshooting S3 and S3Guard

It can be a bit troublesome to get the S3A connector to work, with classpath and authentication being the usual trouble spots. Use the tips provided in the following links to troubleshoot errors.

S3: <https://aws.amazon.com/premiumsupport/knowledge-center/>

S3Guard: https://hadoop.apache.org/docs/current3/hadoop-aws/tools/hadoop-aws/troubleshooting_s3a.html

Related Information

[Encrypting Data on S3](#)

Working with Google Cloud Storage

Cloudera Data Platform Data Centre allows you to configure access from a cluster to Google Cloud Storage (GCS) in order to access cloud data.

Configuring Access to Google Cloud Storage

Access to Google Cloud Storage can be configured separately for each cluster by providing the service account email address.

Access from a cluster to a Google Cloud Storage is possible through a [service account](#). Configuring access to Google Cloud Storage involves the following steps.

Table 4: Overview of Configuring Access to Google Cloud Storage

Step	Considerations
Creating a service account on Google Cloud Platform and generating a key associated with it.	- You may need to contact your Google Cloud Platform admin in order to complete these steps. - If you already have a service account, you do not need to perform these steps as long as you are able to provide the service account key. If you have a service account but do not know the service account key, you should be able to generate a new key.
Creating a role on Google Cloud Platform with sufficient permissions to access storage buckets.	- You may need to contact your Google Cloud Platform admin in order to complete these steps. - This is a one time operation, and the same role can be used across different service accounts and storage buckets.
Modifying permissions of the Google Cloud Storage bucket so that you can access it by using your service account key.	- You may need to contact your Google Cloud Platform admin in order to complete these steps. - You should perform these steps for each bucket that you want to access. - You do not need to perform these steps if your service account has project-wide access to all buckets on the account.
Configuring credentials via Cloudera Manager.	- These configuration steps are appropriate for a single-user cluster. - Only one configuration per cluster is recommended; that is, you should use one service account per cluster. If required, it is possible to use multiple service accounts with the same cluster; in that case, each job-specific configuration should be changed to use the desired service account.

Create a GCP Service Account

You must create a Google Cloud Platform service account and generate an access key (in the JSON format). If you are using a corporate GCP account, it is likely that only your GCP admin can perform these steps. Example steps are described below.

These steps assume that you have a Google Cloud Platform account. If you do not have one, you can create it at <https://console.cloud.google.com>.

Steps

1. In the Google Cloud Platform web console, navigate to IAM & admin Service accounts:
2. Click +Create Service Account.

3. Provide the following information:

- Under Service account name, provide some name for your service account.
- Under Role, select the project-level roles that the account should have.
- Check Furnish a new private key and select JSON.

Create service account

Service account name [?]

Role [?]

Service account ID

☒ **Furnish a new private key**
Downloads a file that contains the private key. Store the file securely because this key can't be recovered if lost.

Key type

☒ **JSON**
Recommended

☐ **P12**
For backward compatibility with code using the P12 format

☐ **Enable G Suite Domain-wide Delegation**
Allows this service account to be authorized to access all users' data on a G Suite domain without manual authorization on their part. [Learn more](#)

CANCEL **CREATE**

4. Click Create and the file containing the key will be downloaded onto your machine. The name of the key file is usually long and contains spaces, so you may want to rename the file.

Later you will need to place this key on your cluster nodes.


Create a Custom Role

Specific permissions are required for the Google Cloud Storage Connector to access buckets. This set of permissions is the combination of the permissions associated with the existing [Google Cloud IAM Role](#) called "Storage Object Admin" and the [Google Cloud IAM Permission](#) called "storage.buckets.get".

- In the Google Cloud Platform web console, navigate to IAM & admin > Roles
- Click on +Create Role.
- Provide the following:
 - Enter a title under Title
 - Enter the ID under ID
 - Under Role launch stage select General Availability

4. Click on Add Permissions and add the following permissions:

- storage.bucket.get
- storage.objects.create
- storage.objects.delete
- storage.objects.get
- storage.objects.getIamPolicy
- storage.objects.list
- storage.objects.setIamPolicy
- storage.objects.update



5. Once done adding permissions, click on Create.

After performing these steps, a new role will be created.

Modify GCS Bucket Permissions

You or your GCP admin must set the bucket permissions so that your service account has access to the bucket that you want to access from the cluster. The IAM role created in the previous step, is the minimum role required to access the cluster. Example steps are described below.


1. In the Google Cloud Platform web console, navigate to Storage > Browser.
2. Find the bucket for which you want to edit permissions.

3. Click the  and select Edit bucket permissions:

4. In the Permissions tab set the bucket-level permissions:

- Click on Add members and enter the service account created earlier.
- Under Roles, select the IAM role created in the previous step. The role should be available under Custom.

- When done, click Add.



After performing these steps, the bucket-level permissions will be updated.

Configure Access to GCS from Your Cluster

After obtaining the service account key, perform these steps on your cluster. The steps below assume that your service account key is called `google-access-key.json`. If you choose a different name, make sure to update the commands accordingly.

1. In Cloudera Manager UI, set the following three properties under `hdfs core-site.xml`. Navigate to Clusters > HDFS > Configuration > Advanced > Add property under Cluster-wide Advanced Configuration Snippet (Safety Valve) for `core-site.xml`.
 - Set the following properties: `fs.gs.auth.service.account.email=<VALUE1>` `fs.gs.auth.service.account.private.key.id=<VALUE2>` `fs.gs.auth.service.account.private.key=<VALUE3>` You can obtain the values for these parameters as follows:

Parameter	Value
<code>fs.gs.auth.service.account.email</code>	The <code>client_email</code> field extracted from the credential's JSON file.
<code>fs.gs.auth.service.account.private.key.id</code>	The <code>private_key_id</code> field extracted from the credential's JSON file.
<code>fs.gs.auth.service.account.private.key</code>	The <code>private_key</code> field extracted from the credential's JSON file.

The JSON key file downloaded in the previous step is in plain text. Open the file in your favorite text editor to extract the relevant values needed in the above configuration.



Note: For enhanced security, these values can also be configured using [Hadoop CredentialProvider](#).

- Configure the following properties if they're not already set by Cloudera Manager `fs.gs.working.dir=/` `fs.gs.path.encoding=uri-path`



Note: Setting `fs.gs.working.dir` configures the initial working directory of a GHFS instance. This should always be set to `/`. Setting `fs.gs.path.encoding` sets the path encoding to be used, and allows for spaces in the filename. This should always be set to `"uri-path"`.

2. Save the configuration change and restart affected services. Additionally - depending on what services you are using - you must restart other services that access cloud storage such as Spark Thrift Server, HiveServer2, and Hive Metastore; These will not be listed as affected by Cloudera Manager, but require a restart to pick up the configuration changes.
3. Test access to the Google Cloud Storage bucket by running a few commands from any cluster node. For example, you can use the command listed below (replace “mytestbucket” with the name of your bucket): `hadoop fs -ls gs://mytestbucket/`

After performing these steps, you should be able to start working with the Google Cloud Storage bucket(s).

Additional Configuration Options for GCS

You may optionally set the following properties related to Google Cloud Storage.

Table 5: Optional Properties Related to Google Cloud Storage

Property	Description
<code>fs.gs.project.id</code>	Allows you to enter Google Cloud's Project ID with access to configured GCS buckets. By default, this option is unset.
<code>fs.gs.block.size</code>	This does not have any effect on storage but allows you to change the way split sizes are computed. The value should be in bytes. We recommend that you set this to the HDFS block size on the cluster, or 134217728 for a block size of 128MB.

Working with the ABFS Connector

Cloudera Data Platform allows you to configure access from a cluster to Azure in order to access cloud data.

Introduction to Azure Storage and the ABFS Connector

The Hadoop-Azure module provides support for Azure Data Lake Storage Gen2 storage layer through the `abfs` connector.

#Azure Data Lake Storage (ADLS) Gen2 combines the features of Azure Blob storage and Azure Data Lake Storage Gen1. In addition to the existing features of both the services, an important part of Azure Data Lake Storage Gen2 is the addition of [hierarchical namespace](#) to Blob storage. The hierarchical namespace feature processes operations such as moving, renaming, and deletings directories by updating a single entry (the parent directory). This ensures a significant improvement in performance of query engines writing data to the store, including MapReduce, Spark, Hive, and DistCp. You can also set permissions on a directory instead of per file basis.



Note: Hierarchical Namespace feature is available only if the container is created with the namespace support. You cannot enable Hierarchical Namespaces on an existing storage account.

Azure Blob Storage

The Azure Storage data model presents three core concepts:

- **Storage Account:** All access is done through a storage account.
- **Container:** A container is a grouping of multiple blobs. A storage account may have multiple containers. In Hadoop, an entire file system hierarchy is stored in a single container.
- **Blob:** A file of any type and size stored with the existing Windows Azure Storage Blob (wasb) connector

Features of the ABFS Connector

The ABFS connector can be used as a replacement for HDFS on Hadoop clusters deployed in Azure infrastructure. Some of the features of the ABFS connector are as follows:

- Supports reading and writing data stored in an Azure Blob Storage account
- Helps to perform hadoop operations on Azure datastores
- Provides a consistent view of the storage across all clients
- Enables using a simple `abfs://` url to access containers and directories
- Presents a hierarchical file system view by implementing the standard Hadoop File System interface
- Supports configuration of multiple Azure Blob Storage accounts
- Acts as a source or destination of data in Hadoop MapReduce, Apache Hive, Apache Spark

Feature Comparisons

ADLS Gen 2 is where all future development of Azure Big Data storage is taking place, in the cloud server as well as the client connector. In contrast, ADLS Gen 1 must be considered a **maintenance only** data store, which is not being rolled out across more Azure regions.

Feature	Azure Storage	ADLS Gen 1	ADLS Gen 2
Broadly supported in applications	Yes	No	Yes in non-hierarchical; growing in hierarchical
Scales to many petabytes	No	Yes	Yes
Available in all Azure region	Yes	No	Yes
Interoperability	ADLS Gen 2 in non-hierarchical	none	Azure Storage
Directories with permissions	No	Yes	Yes

Differences between ADLS Gen 1 and ADLS Gen 2

ADLS Gen 2 should be considered as a reimplementation of the ADLS Gen 1 features, but integrated with the original Azure Storage.

Features of ADLS Gen 2

- Supports the Hadoop FileSystem API, with directories, file and directory permissions, and other key features.
- Reads and writes data stores in the original Azure Storage (which has previously used the wasb:// URL)
- No integration with ADLS Gen1. The adls:// connector must be used there.
- Available in all Azure regions.
- If an ADLS Gen 2 account is created "without hierarchical namespaces" then the wasb:// connector can read/write data stored in ADLS Gen 2.
- Capable of storing many Petabytes of data.

Setting up and configuring the ABFS connector

You must have an Azure storage account with hierarchical namespace enabled and Azure container prior to configuring the ABFS connector.

About this task

You can use the following steps to create a new storage account, create a new container, and configure the ABFS connector:

Procedure

1. Create Azure storage account

Every storage account must belong to an Azure resource group. A resource group is a logical container for grouping your Azure services. When you create a storage account, you have the option to either create a new resource group, or use an existing resource group.

You can create an Azure storage account using Azure CLI or Azure portal. When creating a Storage Account, you must ensure to enable namespace support by selecting the **Hierarchical Namespace** option. For information on creating an Azure storage account, see [Create a storage account](#).

2. Create Azure Container

You must create a container to organize the blobs. One Azure storage account can have multiple containers, each with the container name as the user information field of the URI used to reference it.

For example, the container `container1` in the storage account will have the URL `abfs://container1@<storage_account>.dfs.core.windows.net/`.

For information on creating a container in Azure, see [Create a container](#).

3. Configure ABFS

You can configure access credentials to authorise access to Azure containers. For information on configuring ABFS, see [Configuring ABFS](#).



Note: Delete Azure storage account - Deleting a storage account deletes the entire account, including all data in the account, and cannot be undone. For information about deleting an Azure storage account, see [Delete a storage account](#).

Configuring the ABFS Connector

You can configure access credentials to authorise access to Azure containers in multiple ways including IDBroker, Shared Key, Managed Instance, and Shared Access Signature.

Authenticating with ADLS Gen2

Authentication for ABFS is granted by Azure Active Directory. The authentication mechanism is set using the `fs.azure.account.auth.type` (or the account specific variant) property in the `core-site.xml` file.

Configuring Access to Azure on CDP Public Cloud

IDBroker is a REST API built as part of Apache Knox's authentication services. It allows an authenticated user to exchange a set of credentials or a token for cloud vendor access tokens. IDBroker manages mapping LDAP users to FreeIPA cloud identities for data access. It performs identity mapping for access to object stores.

For information on how IDBroker works in CDP, see [ADLS Gen2 and managed identities](#) in the *Management Console* documentation.

Configuring Access to Azure on CDP Private Cloud Base


You can use Shared Key, Managed Instance, Shared Access Signature, and so on to configure access credentials to authorise access to Azure containers. For example, a shared key account can be configured for use regardless of which account is accessed with the property `fs.azure.account.key` or you can configure an identity to be used only for a specific storage account with `fs.azure.account.key.<BUCKET NAME>.blob.core.windows.net`.

Before you begin

After you create a storage account, Azure generates two 512-bit storage account access keys. You can use these keys to authorize access to data in your storage account. For information on how to access this Shared Key, see [View account access keys](#). To configure access to the Azure container, add the Shared Key details in the `core-site.xml` file using Cloudera Manager.

Procedure

1. In Cloudera Manager, select Clusters > HDFS service.



2. Click the Configuration tab.
3. Search for core-site.
4. In the Cluster-wide Advanced Configuration Snippet (Safety Valve) for core-site.xml option, click the + sign and add the below properties:

Name: fs.azure.account.auth.type.<account_name>.dfs.core.windows.net
Value: <Shared_Key> (or_any_other_Auth_type)

Name: fs.azure.account.key.<your_storage_account_name>.dfs.core.windows.net

Value: <Access_key>

Name	fs.azure.account.auth.type.<YOUR STORAGE ACC NAME>.dfs.core.windows.net	
Value	SharedKey (OR ANY OTHER AUTH TYPE)	
Description		
	☐ Final	
Name	fs.azure.account.key.<YOUR STORAGE ACC NAME>.dfs.core.windows.net	
Value	<YOUR ACCESS KEY>	
Description		
	☐ Final	

HDFS-1 (Service-Wide) View as XML

(Safety Valve) for core-sit... Save Changes (CTR)

5. Click Save Changes.

6.



Next to the HDFS title, click ig>

Restart and Redeploy to restart and redeploy the configurations.

ADLS Proxy Setup

The ADLS connector uses the JVM proxy settings to control its proxy setup.

The [Oracle Java documentation](#) covers the options to set.

As the ADLS connector uses HTTPS, the https.proxy options are those which must be configured. See [DistCp and Proxy Settings](#) for the specifics of how to set these proxy settings in DistCp (or indeed, any MapReduce job).

Performance and Scalability

Like all Azure storage services, the Azure Datalake Gen 2 store offers a fully consistent view of the store, with a complete Create, Read, Update, and Delete operation consistency for data and metadata.

Hierarchical namespaces vs. non-namespaces

For containers with hierarchical namespaces, the scalability numbers, in Big-O Notation, are as follows:

Operation	Scalability
File Rename	$O(1)$
File Delete	$O(1)$
Directory Rename:	$O(1)$
Directory Delete	$O(1)$

For non-namespace stores, the scalability numbers are as follows:

Operation	Scalability
File Rename	$O(1)$
File Delete	$O(1)$
Directory Rename:	$O(\text{files})$
Directory Delete	$O(\text{files})$

Source: [Performance_and_Scalability](#)

Flush options

The Azure Blob File System and OutputStream flush options are enabled by default. These flush options have an impact on performance. Those applications which call `flush()` frequently, for example, with every write of a line, might show poor performance. Hence, you must disable the flush option if your application does not need it.

- Azure Blob File System Flush Options (`fs.azure.enable.flush`) - renders ABFS flush APIs - `HFlush()` and `HSync()`, to be no-op. Both the APIs ensure that data persists.
- OutputStream Flush Options (`fs.azure.disable.outputstream.flush`) - renders OutputStream `Flush()` API to be a no-op in `AbfsOutputStream`. `Hflush()` being the only documented API that can provide persistent data transfer, `flush()` also attempting to persist buffered data will lead to performance issues.

Using ABFS using CLI

After you configure access in the `core-site.xml` file, you can access your cluster using the CLI. You can run Hadoop file system commands, DistCP commands, create Hive tables, and so on using the CLI.

Hadoop File System commands

You can execute Hadoop file system commands using CLI on your cluster.

- Access your cluster by using the URL of the container.

```
abfs://<NAME OF CONTAINER>@<NAME OF ACCOUNT>.dfs.core.windows.net/
```

- Create a directory using the `mkdir` command. For example,

```
hadoop fs -mkdir abfs://abfscontainer@abfstorageacc.dfs.core.windows.net/
myDir/
hadoop fs -ls abfs://abfscontainer@abfstorageacc.dfs.core.windows.net/

Found 2 items

drwxr-xr-x - root root 0 2020-05-20 15:14
abfs://abfscontainer@abfstorageacc.dfs.core.windows.net/myDir
drwxr-xr-x - root root 0 2020-05-20 12:50
abfs://abfscontainer@abfstorageacc.dfs.core.windows.net/test
```

Similarly, you can use the `put` command to add a file to one of the directories, `ls` command to list the items in your cluster, and `cat` command to read the contents of the file.



Note: If you name a file with the same file name that is already present in the directory, the existing file is not overwritten.

Create a table in Hive

You can create, modify, update, and remove tables in Hive using beeline or any other tool to access Hive.

1. Enter the beeline command shell by `beeline` command in your cluster:

```
~ beeline
```

2. Enter the database you want to access.

```
~ use <DATABASE_NAME>;
```

Or create and use a new database. In this following example, `abfsdb` is the name of the database.

```
create database abfsdb;
~ use abfsdb;
```

3. Create a table inside the container in a directory named `table_1`. If the directory does not exist, it is automatically created:

```
~ create external table myTable(key STRING, value INT) location
'abfs://abfscontainer@abfstorageacc.dfs.core.windows.net/table_1/';
```

4. View the table structure using the `show` command:

```
~ show create table myTable;
INFO : Compiling command(queryId=hive_20200520153116_301af680-9630-49d1-af40-3dfa5349e52a): show create table myTable
INFO : Semantic Analysis Completed (retrial = false)
INFO : Created Hive schema: Schema(fieldSchemas:[FieldSchema(name:createtab_stmt, type:string, comment:from deserializer)], properties:null)
INFO : Completed compiling command(queryId=hive_20200520153116_301af680-9630-49d1-af40-3dfa5349e52a); Time taken: 0.052 seconds
INFO : Executing command(queryId=hive_20200520153116_301af680-9630-49d1-af40-3dfa5349e52a): show create table myTable
INFO : Starting task [Stage-0:DDL] in serial mode
INFO : Completed executing command(queryId=hive_20200520153116_301af680-9630-49d1-af40-3dfa5349e52a); Time taken: 0.072 seconds
INFO : OK

+-----+
| createtab_stmt |
```

```

+-----+
| CREATE EXTERNAL TABLE `myTable` (
|   `key` string,
|   `value` int)
| ROW FORMAT SERDE
|   'org.apache.hadoop.hive.serde2.lazy.LazySimpleSerDe' |
| STORED AS INPUTFORMAT
|   'org.apache.hadoop.mapred.TextInputFormat'
| OUTPUTFORMAT
|   'org.apache.hadoop.hive.ql.io.HiveIgnoreKeyTextOutputFormat' |
| LOCATION
|   'abfs://abfscontainer@abfstorageacc.dfs.core.windows.net/table_1' |
| TBLPROPERTIES (
|   'bucketing_version'='2',
|   'transient_lastDdlTime'='1589988617')
+-----+
14 rows selected (0.162 seconds)

```

After the table is created inside the Azure storage, it behaves like a regular table and you can use all the `hql` commands. For example, to insert values in the table, run `~ insert into myTable values("myKey", 1);`


Accessing Azure Storage account container from spark-shell

You can use spark-shell to query the files that are stored in the Azure Storage account. You should be able to access spark as an `hdfs` user using the `~ sudo -u hdfs -s` command.

```

~ spark-shell
Setting default log level to "WARN".
To adjust logging level use sc.setLogLevel(newLevel). For SparkR, use set
LogLevel(newLevel).
20/05/20 16:35:32 WARN cluster.YarnSchedulerBackend$YarnSchedulerEndpoint: A
ttempted to request executors before the AM has registered!
Spark context available as 'sc' (master = yarn, app id = application_1589987
399184_0004).
Spark session available as 'spark'.
Welcome to

```



version 2.4.0.7.1.1.0-413

```

Using Scala version 2.11.12 (OpenJDK 64-Bit Server VM, Java 1.8.0_232)
Type in expressions to have them evaluated.
Type :help for more information.

```

```

scala> val sampleRDD = sc.textFile("abfs://abfscontainer@abfstorageacc.dfs
.core.windows.net/myDir/testingFile.txt")
sampleRDD: org.apache.spark.rdd.RDD[String] = abfs://abfscontainer@abfstor
ageacc.dfs.core.windows.net/myDir/testingFile.txt MapPartitionsRDD[1] at tex
tFile at <console>:24

```

```

scala> sampleRDD.collect().foreach(println)
testing the hadoop fs commands on azure.

```

Hence, after accessing the azure container, the data in `sampleRDD` would work like any other text file. Now, you can use any spark operation on these files. For example,

- Find the word count of a particular word:

```

scala> sampleRDD.filter(line => line.contains("azure")).count()
res4: Long = 1

```

- Use wordcount by MapReduce, as popularized by Hadoop. Spark can implement MapReduce flows easily:

```
scala> val wordcount = sampleRDD.flatMap(line => line.split(" ")).map(word
=> (word,1)).reduceByKey(_+_)
wordcount: org.apache.spark.rdd.RDD[(String, Int)] = ShuffledRDD[7] at
reduceByKey at <console>:26
scala> wordcount.collect()
res7: Array[(String, Int)] = Array((commands,1), (testing,1), (hadoop,1),
(on,1), (fs,1), (azure.,1), (the,1))
```

Copying data with Hadoop DistCp

DistCp (distributed copy) is a tool used to copy files in large inter-cluster and intra-cluster environments. It uses MapReduce to affect its distribution, error handling and recovery, and reporting. It expands a list of files and directories into input to map tasks, each of which copy a partition of the files specified in the source list.

The following are some of the examples of distcp commands with object stores:

- Copying between directories in an object store

```
~ hadoop distcp
abfs://abfscontainer@abfstorageacc.dfs.core.windows.net/myDir/testingFi
le.txt \ abfs://abfscontainer@abfstorageacc.dfs.core.windows.net/test/

20/05/21 08:48:09 INFO mapreduce.Job: Job job_1589987399184_0005
completed successfully

~hadoop fs -ls abfs://abfscontainer@abfstorageacc.dfs.core.windows.net/tes
t/

Found 1 items

-rw-r--r--    1 hdfs hdfs          41 2020-05-21 08:48
abfs://abfscontainer@abfstorageacc.dfs.core.windows.net/test/testingFil
e.txt
```

- Copying between two different object stores

```
~ hadoop distcp
abfs://abfscontainer@abfstorageacc.dfs.core.windows.net/myDir/testingFi
le.txt \ abfs://mycontainer@mystoragehastoexist.dfs.core.windows.net/new
test/

20/05/21 08:53:26 INFO mapreduce.Job: Job job_1589987399184_0007
completed successfully
~ hadoop fs -ls
abfs://mycontainer@mystoragehastoexist.dfs.core.windows.net/newtest/

Found 1 items

-rw-r--r--    1 hdfs hdfs          41 2020-05-21 08:53
abfs://mycontainer@mystoragehastoexist.dfs.core.windows.net/newtest/tes
tingFile.txt
```

For more information about the DistCp commands, see [DistCP](#) documentation.

DistCp and Proxy Settings

When using DistCp to back up data from an on-site Hadoop cluster, proxy settings may need to be set so as to reach the cloud store. For most of the stores, these proxy settings are hadoop configuration options which must be set in `core-site.xml`, or as options to the DistCp command.

ADLS uses the JVM proxy settings, which need to be set in DistCp's map and reduce processes. This can be done through the `mapreduce.map.java.opts` and `mapreduce.reduce.java.opts` options respectively.

```
export DISTCP_PROXY_OPTS="-Dhttps.proxyHost=web-proxy.example.com -Dhttps.pr
oxyPort=80"
hadoop distcp \
  -D mapreduce.map.java.opts="$DISTCP_PROXY_OPTS" \
  -D mapreduce.reduce.java.opts="$DISTCP_PROXY_OPTS" \
  -update -skipcrccheck -numListstatusThreads 40 \
  hdfs://namenode:8020/users/alice adl://backups.azuredatalakestore.net/us
ers/alice
```

Without these settings, even though access to ADLS may work from the command line, distcp access can fail with Error fetching access token.

ADLS Trash Folder Behavior

If the `fs.trash.interval` property is set to a value other than zero on your cluster and you do not specify the `-skipTrash` flag with your `rm` command when you remove files, the deleted files are moved to the trash folder in your ADLS account. The trash folder in your ADLS account is located at `adl://your_account.azuredatalakestore.net/user/user_name/.Trash/current/`.

For more information about HDFS trash, see [Configuring HDFS Trash](#).

Troubleshooting ABFS

You might encounter issues when configuring the ABFS connector. The issues are usually related to classpath, network, and authentication. For tips to troubleshoot these issues, see <https://hadoop.apache.org/docs/current/hadoop-azure/abfs.html#Troubleshooting>.