

Accessing Apache HBase

Date published: 2020-02-29

Date modified: 2023-04-05



Legal Notice

© Cloudera Inc. 2025. All rights reserved.

The documentation is and contains Cloudera proprietary information protected by copyright and other intellectual property rights. No license under copyright or any other intellectual property right is granted herein.

Unless otherwise noted, scripts and sample code are licensed under the Apache License, Version 2.0.

Copyright information for Cloudera software may be found within the documentation accompanying each component in a particular release.

Cloudera software includes software from various open source or other third party projects, and may be released under the Apache Software License 2.0 (“ASLv2”), the Affero General Public License version 3 (AGPLv3), or other license terms. Other software included may be released under the terms of alternative open source licenses. Please review the license and notice files accompanying the software for additional licensing information.

Please visit the Cloudera software product page for more information on Cloudera software. For more information on Cloudera support services, please visit either the Support or Sales page. Feel free to contact us directly to discuss your specific needs.

Cloudera reserves the right to change any products at any time, and without notice. Cloudera assumes no responsibility nor liability arising from the use of products, except as expressly agreed to in writing by Cloudera.

Cloudera, Cloudera Altus, HUE, Impala, Cloudera Impala, and other Cloudera marks are registered or unregistered trademarks in the United States and other countries. All other trademarks are the property of their respective owners.

Disclaimer: EXCEPT AS EXPRESSLY PROVIDED IN A WRITTEN AGREEMENT WITH CLOUDERA, CLOUDERA DOES NOT MAKE NOR GIVE ANY REPRESENTATION, WARRANTY, NOR COVENANT OF ANY KIND, WHETHER EXPRESS OR IMPLIED, IN CONNECTION WITH CLOUDERA TECHNOLOGY OR RELATED SUPPORT PROVIDED IN CONNECTION THEREWITH. CLOUDERA DOES NOT WARRANT THAT CLOUDERA PRODUCTS NOR SOFTWARE WILL OPERATE UNINTERRUPTED NOR THAT IT WILL BE FREE FROM DEFECTS NOR ERRORS, THAT IT WILL PROTECT YOUR DATA FROM LOSS, CORRUPTION NOR UNAVAILABILITY, NOR THAT IT WILL MEET ALL OF CUSTOMER’S BUSINESS REQUIREMENTS. WITHOUT LIMITING THE FOREGOING, AND TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, CLOUDERA EXPRESSLY DISCLAIMS ANY AND ALL IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, QUALITY, NON-INFRINGEMENT, TITLE, AND FITNESS FOR A PARTICULAR PURPOSE AND ANY REPRESENTATION, WARRANTY, OR COVENANT BASED ON COURSE OF DEALING OR USAGE IN TRADE.

Contents

Use the HBase shell.....	4
Virtual machine options for HBase Shell.....	4
Script with HBase Shell.....	4
Use the HBase command-line utilities.....	5
Use the HBase APIs for Java.....	11
Use the HBase REST server.....	12
Installing the REST Server using Cloudera Manager.....	12
Using the REST API.....	12
Using the REST Proxy API.....	19
Use the Apache Thrift Proxy API.....	20
Use the Hue HBase app.....	25

Use the HBase shell

You can use the HBase Shell from the command line interface to communicate with HBase. In CDP, you can create a namespace and manage it using the HBase shell. Namespaces contain collections of tables and permissions, replication settings, and resource isolation.

In CDP, you need to SSH into an HBase node before you can use the HBase Shell. For example, to SSH into an HBase node with the IP address 10.10.10.10, you must use the command:

```
ssh <USERNAME>@10.10.10.10
```



Note: You must use your IPA password for authentication.

After you have started HBase, you can access the database in an interactive way by using the HBase Shell, which is a command interpreter for HBase which is written in Ruby. Always run HBase administrative commands such as the HBase Shell, hbck, or bulk-load commands as the HBase user (typically hbase).

```
hbase shell
```

You can use the following commands to get started with the HBase shell:

- To get help and to see all available commands, use the help command.
- To get help on a specific command, use help "command". For example:

```
hbase> help "create"
```

- To remove an attribute from a table or column family or reset it to its default value, set its value to nil. For example, use the following command to remove the KEEP_DELETED_CELLS attribute from the f1 column of the users table:

```
hbase> alter 'users', { NAME => 'f1', KEEP_DELETED_CELLS => nil }
```

- To exit the HBase Shell, type quit.

Virtual machine options for HBase Shell

You can set variables for the virtual machine running HBase Shell, by using the HBASE_SHELL_OPTS environment variable. This example sets several options in the virtual machine.

This example sets several options in the virtual machine.

```
$ HBASE_SHELL_OPTS="-verbose:gc -XX:+PrintGCApplicationStoppedTime -XX:+PrintGCDateStamps  
-XX:+PrintGCDetails -Xloggc:$HBASE_HOME/logs/gc-hbase.log" ./bin/hbase  
shell
```

Script with HBase Shell

You can use HBase shell in your scripts. You can also write Ruby scripts for use with HBase Shell. Example Ruby scripts are included in the hbase-examples/src/main/ruby/ directory.

The non-interactive mode allows you to use HBase Shell in scripts, and allow the script to access the exit status of the HBase Shell commands. To invoke non-interactive mode, use the `-n` or `--non-interactive` switch. This small example script shows how to use HBase Shell in a Bash script.

```
#!/bin/bash
echo 'list' | hbase shell -n
status=$?
if [ $status -ne 0 ]; then
    echo "The command may have failed."
fi
```

Successful HBase Shell commands return an exit status of 0. However, an exit status other than 0 does not necessarily indicate a failure, but should be interpreted as unknown. For example, a command may succeed, but while waiting for the response, the client may lose connectivity. In that case, the client has no way to know the outcome of the command. In the case of a non-zero exit status, your script should check to be sure the command actually failed before taking further action.

You can use the `get_splits` command, which returns the split points for a given table:

```
hbase> get_splits 't2'
Total number of splits = 5

=> ["", "10", "20", "30", "40"]
```

Use the HBase command-line utilities

Besides the HBase Shell, HBase includes several other command-line utilities, which are available in the `hbase/bin/` directory of each HBase host. This topic provides basic usage instructions for the most commonly used utilities.

PerformanceEvaluation

The PerformanceEvaluation utility allows you to run several preconfigured tests on your cluster and reports its performance. To run the PerformanceEvaluation tool, use the `bin/hbase pecommand`.

```
$ hbase pe

Usage: java org.apache.hadoop.hbase.PerformanceEvaluation \
  <OPTIONS> [-D<property=value>]* <command> <nclients>

Options:
  nomapreduce      Run multiple clients using threads (rather than use mapreduce)
  rows             Rows each client runs. Default: One million
  size             Total size in GiB. Mutually exclusive with --rows. Default: 1.0.
  sampleRate       Execute test on a sample of total rows. Only supported by randomRead.
  andomRead        Default: 1.0
  traceRate        Enable HTrace spans. Initiate tracing every N rows. Default: 0
  table            Alternate table name. Default: 'TestTable'
  multiGet         If >0, when doing RandomRead, perform multiple gets instead of single gets.
  of single        Default: 0
  compress         Compression type to use (GZ, LZ0, ...). Default: 'NONE'
  flushCommits     Used to determine if the test should flush the table. Default: false
  writeToWAL       Set writeToWAL on puts. Default: True
```

```

autoFlush          Set autoFlush on htable. Default: False
oneCon             all the threads share the same connection. Default: False
presplit           Create presplit table. Recommended for accurate perf analy
sis (see           guide). Default: disabled
inmemory          Tries to keep the HFiles of the CF inmemory as far as possi
ble. Not           guaranteed that reads are always served from memory. Defa
ult: false
usetags            Writes tags along with KVs. Use with HFile V3. Default:
false
numoftags          Specify the no of tags that would be needed. This works o
nly if usetags     is true.
filterAll          Helps to filter out all the rows on the server side there
by not returning   anything back to the client. Helps to check the server si
de performance.    Uses FilterAllFilter internally.
latency            Set to report operation latencies. Default: False
bloomFilter        Bloom filter type, one of [NONE, ROW, ROWCOL]
valueSize          Pass value size to use: Default: 1024
valueRandom        Set if we should vary value size between 0 and 'valueSiz
e'; set on read    for stats on size: Default: Not set.
valueZipf          Set if we should vary value size between 0 and 'valueSize'
in zipf form:      Default: Not set.
period            Report every 'period' rows: Default: opts.perClientRunRo
ws / 10
multiGet           Batch gets together into groups of N. Only supported by ran
domRead.           Default: disabled
addColumns         Adds columns to scans/gets explicitly. Default: true
replicas           Enable region replica testing. Defaults: 1.
splitPolicy        Specify a custom RegionSplitPolicy for the table.
randomSleep        Do a random sleep before each get between 0 and entered v
alue. Defaults: 0
columns            Columns to write per row. Default: 1
caching            Scan caching to use. Default: 30

Note: -D properties will be applied to the conf used.
For example:
-Dmapreduce.output.fileoutputformat.compress=true
-Dmapreduce.task.timeout=60000
Command:
append            Append on each row; clients overlap on keyspace so some c
oncurrent          operations
checkAndDelete     CheckAndDelete on each row; clients overlap on keyspace so
some concurrent   operations
checkAndMutate     CheckAndMutate on each row; clients overlap on keyspace so
some concurrent   operations
checkAndPut        CheckAndPut on each row; clients overlap on keyspace so s
ome concurrent    operations
filterScan         Run scan test using a filter to find a specific row based
on it's value      (make sure to use --rows=20)
increment          Increment on each row; clients overlap on keyspace so some
concurrent         operations

```

```

randomRead      Run random read test
randomSeekScan  Run random seek and scan 100 test
randomWrite     Run random write test
scan            Run scan test (read every row)
scanRange10     Run random seek scan with both start and stop row (max 10
rows)
scanRange100    Run random seek scan with both start and stop row (max 100
rows)
scanRange1000   Run random seek scan with both start and stop row (max 1000
rows)
scanRange10000  Run random seek scan with both start and stop row (max 1
0000 rows)
sequentialRead  Run sequential read test
sequentialWrite Run sequential write test
Args:
nclients        Integer. Required. Total number of clients (and HRegionS
ervers)
running: 1 <= value <= 500
Examples:
To run a single client doing the default 1M sequentialWrites:
$ bin/hbase org.apache.hadoop.hbase.PerformanceEvaluation sequentialWrite 1
To run 10 clients doing increments over ten rows:
$ bin/hbase org.apache.hadoop.hbase.PerformanceEvaluation --rows=10 --noma
pred increment 10

```

LoadTestTool

The LoadTestTool utility load-tests your cluster by performing writes, updates, or reads on it. To run the LoadTest Tool, use the `bin/hbase ltt` command. To print general usage information, use the `-h` option.

```

$ bin/hbase ltt -h

Options:
-batchupdate      Whether to use batch as opposed to separate
updates for every column in a row
-bloom <arg>      Bloom filter type, one of [NONE, ROW, ROWC
OL]
-compression <arg> Compression type, one of [LZO, GZ, NONE, SN
APPY, LZ4]
-data_block_encoding <arg> Encoding algorithm (e.g. prefix compress
ion) to use for data blocks in the test column family, one of
[NONE, PREFIX, DIFF, FAST_DIFF, PREFIX_T
REE].
-deferredlogflush Enable deferred log flush.
-encryption <arg> Enables transparent encryption on the test
table, one of [AES]
-families <arg>    The name of the column families to use se
parated by comma
-generator <arg>   The class which generates load for the too
l. Any args for this class can be passed as colon separated after c
lass name
-h, --help         Show usage
-in_memory         Tries to keep the HFiles of the CF inmemory
as far as possible. Not guaranteed that reads are always served fro
m inmemory
-init_only         Initialize the test table only, don't do
any loading

```

-key_window <arg> and writes for concurrent	The 'key window' to maintain between reads
-max_read_errors <arg> erate before terminating all	write/read workload. The default is 0. The maximum number of read errors to tol
-mob_threshold <arg> will use the MOB write path	reader threads. The default is 10. Desired cell size to exceed in bytes that
-multiget_batchsize <arg> arate gets for every	Whether to use multi-gets as opposed to sep
-multiput eparate puts for every	column in a row Whether to use multi-puts as opposed to s
-num_keys <arg>	column in a row The number of keys to read/write
-num_regions_per_server <arg> er. Defaults to 5.	Desired number of regions per region serv
-num_tables <arg> is specified, load test tool	A positive integer number. When a number n
value becomes table name prefix.	will load n table parallely. -tn parameter
_n	Each table name is in format <tn>_1...<tn>
-read <arg>	<verify_percent>[:<#threads=20>]
-reader <arg>	The class for executing the read requests
-region_replica_id <arg>	Region replica id to do the reads from
-region_replication <arg>	Desired number of replicas per region
-regions_per_server <arg> is specified, load test tool	A positive integer number. When a number n
er server	will create the test table with n regions p
-skip_init already exists	Skip the initialization; assume test table
-start_key <arg> ex). The default value is 0.	The first key to read/write (a 0-based ind
-tn <arg>	The name of the table to read or write
-update <arg> to ignore nonce collisions=0>]	<update_percent>[:<#threads=20>][:<#whether
-updater <arg>	The class for executing the update requests
-write <arg> eads=20>]	<avg_cols_per_key>:<avg_data_size>[:<#thr
-writer <arg>	The class for executing the write requests
-zk <arg>	ZK quorum as comma-separated host names w
ithout port numbers	
-zk_root <arg>	name of parent znode in zookeeper

wal

The wal utility prints information about the contents of a specified WAL file. To get a list of all WAL files, use the HDFS command `hadoop fs -ls -R /hbase/WALs`. To run the wal utility, use the `bin/hbase wal` command. Run it without options to get usage information.

```
hbase wal
usage: WAL <filename...> [-h] [-j] [-p] [-r <arg>] [-s <arg>] [-w <arg>]
-h, --help            Output help message
-j, --json            Output JSON
-p, --printvals       Print values
-r, --region <arg>   Region to filter by. Pass encoded region name; e.g.
                    '9192caead6a5a20acb4454ffbc79fa14'
-s, --sequence <arg> Sequence to filter by. Pass sequence number.
-w, --row <arg>      Row to filter by. Pass row name.
```

hfile

The hfile utility prints diagnostic information about a specified hfile, such as block headers or statistics. To get a list of all hfiles, use the HDFS command `hadoop fs -ls -R /hbase/data`. To run the hfile utility, use the `bin/hbase hfilecommand`. Run it without options to get usage information.

```
$ hbase hfile

usage: HFile [-a] [-b] [-e] [-f <arg> | -r <arg>] [-h] [-i] [-k] [-m] [-p]
           [-s] [-v] [-w <arg>]
-a,--checkfamily           Enable family check
-b,--printblocks           Print block index meta data
-e,--printkey              Print keys
-f,--file <arg>           File to scan. Pass full-path; e.g.
                           hdfs://a:9000/hbase/hbase:meta/12/34
-h,--printblockheaders     Print block headers for each block.
-i,--checkMobIntegrity     Print all cells whose mob files are missing
-k,--checkrow              Enable row order check; looks for out-of-order
                           keys
-m,--printmeta             Print meta data of file
-p,--printkv               Print key/value pairs
-r,--region <arg>         Region to scan. Pass region name; e.g.
                           'hbase:meta,,1'
-s,--stats                 Print statistics
-v,--verbose               Verbose output; emits file and meta data
                           delimiters
-w,--seekToRow <arg>      Seek to this row and print all the kvs for this
                           row only
```

hbck

The hbck utility checks and optionally repairs errors in HFiles.



Warning: Running hbck with any of the `-fix` or `-repair` commands is dangerous and can lead to data loss. Contact Cloudera support before running it.

To run hbck, use the `bin/hbase hbck` command. Run it with the `-h` option to get more usage information.

```
-----
NOTE: As of HBase version 2.0, the hbck tool is significantly changed.
In general, all Read-Only options are supported and can be used
safely. Most -fix/ -repair options are NOT supported. Please see usage
below for details on which options are not supported.
-----
```

```
Usage: fsck [opts] {only tables}
where [opts] are:
  -help Display help options (this)
  -details Display full report of all regions.
  -timelag <timeInSeconds> Process only regions that have not experienced
any metadata updates in the last <timeInSeconds> seconds.
  -sleepBeforeRerun <timeInSeconds> Sleep this many seconds before checking
if the fix worked if run with -fix
  -summary Print only summary of the tables and status.
  -metaonly Only check the state of the hbase:meta table.
  -sidelineDir <hdfs://> HDFS path to backup existing meta.
  -boundaries Verify that regions boundaries are the same between META and
store files.
  -exclusive Abort if another hbck is exclusive or fixing.
```

Datafile Repair options: (expert features, use with caution!)

```
-checkCorruptHFiles    Check all Hfiles by opening them to make sure the
                        y are valid
-sidelineCorruptHFiles  Quarantine corrupted HFiles.  implies -checkCorru
                        ptHFiles
```

Replication options

```
-fixReplication    Deletes replication queues for removed peers
```

Metadata Repair options supported as of version 2.0: (expert features, use with caution!)

```
-fixVersionFile    Try to fix missing hbase.version file in hdfs.
-fixReferenceFiles  Try to offline lingering reference store files
-fixHFileLinks     Try to offline lingering HFileLinks
-noHdfsChecking    Don't load/check region info from HDFS. Assumes hbas
e:meta region info is good. Won't check/fix any HDFS issue, e.g. hole, orpha
n, or overlap
-ignorePreCheckPermission  ignore filesystem permission pre-check
```

NOTE: Following options are NOT supported as of HBase version 2.0+.

```
UNSUPPORTED Metadata Repair options: (expert features, use with caution!)
-fix                                Try to fix region assignments. This is for backwards
compatibility
-fixAssignments    Try to fix region assignments. Replaces the old -fix
-fixMeta           Try to fix meta problems. This assumes HDFS region inf
o is good.
-fixHdfsHoles      Try to fix region holes in hdfs.
-fixHdfsOrphans    Try to fix region dirs with no .regioninfo file in hdfs
-fixTableOrphans   Try to fix table dirs with no .tableinfo file in hdfs
(online mode only)
-fixHdfsOverlaps   Try to fix region overlaps in hdfs.
-maxMerge <n>      When fixing region overlaps, allow at most <n> regions
to merge. (n=5 by default)
-sidelineBigOverlaps  When fixing region overlaps, allow to sideline big
overlaps
-maxOverlapsToSideline <n> When fixing region overlaps, allow at most <
n> regions to sideline per group. (n=2 by default)
-fixSplitParents    Try to force offline split parents to be online.
-removeParents      Try to offline and sideline lingering parents and keep
daughter regions.
-fixEmptyMetaCells  Try to fix hbase:meta entries not referencing any
region (empty REGIONINFO_QUALIFIER rows)
```

UNSUPPORTED Metadata Repair shortcuts

```
-repair                Shortcut for -fixAssignments -fixMeta -fixHdfsHoles -
fixHdfsOrphans -fixHdfsOverlaps -fixVersionFile -sidelineBigOverlaps -fixRef
erenceFiles -fixHFileLinks
-repairHoles           Shortcut for -fixAssignments -fixMeta -fixHdfsHoles
```

clean

After you have finished using a test or proof-of-concept cluster, the `hbase clean` utility can remove all HBase-related data from ZooKeeper and HDFS.



Warning: The `hbase clean` command destroys data. Do not run it on production clusters, or unless you are absolutely sure you want to destroy the data.

To run the `hbase clean` utility, use the `bin/hbase clean` command. Run it with no options for usage information.

```
$ bin/hbase clean
```

```
Usage: hbase clean (--cleanZk|--cleanHdfs|--cleanAll)
Options:
```

```
--cleanZk    cleans hbase related data from zookeeper.
--cleanHdfs  cleans hbase related data from hdfs.
--cleanAll   cleans hbase related data from both zookeeper and hdfs.
```

Use the HBase APIs for Java

You can use the Apache HBase Java API to communicate with Apache HBase. The Java API is one of the most common ways to communicate with HBase.

The following sample uses Apache HBase APIs to create a table and put a row into that table. The table name, column family name, qualifier (or column) name, and a unique ID for the row are defined. Together, these define a specific cell. Next, the table is created and the text “Hello, World!” is inserted into this cell.

```
import java.io.IOException;
import org.apache.hadoop.conf.Configuration;
import org.apache.hadoop.hbase.HBaseConfiguration;
import org.apache.hadoop.hbase.TableName;
import org.apache.hadoop.hbase.client.*;
import org.apache.hadoop.hbase.util.Bytes;

public class CreateAndPut {
    private static final TableName TABLE_NAME = TableName.valueOf("test_table_example");
    private static final byte[] CF_NAME = Bytes.toBytes("test_cf");
    private static final byte[] QUALIFIER = Bytes.toBytes("test_column");
    private static final byte[] ROW_ID = Bytes.toBytes("row01");
    public static void createTable(final Admin admin) throws IOException {
        if(!admin.tableExists(TABLE_NAME)) {
            TableDescriptor desc = TableDescriptorBuilder.newBuilder(TABLE_NAME)
                .setColumnFamily(ColumnFamilyDescriptorBuilder.of(CF_NAME))
                .build();
            admin.createTable(desc);
        }
    }

    public static void putRow(final Table table) throws IOException {
        table.put(new Put(ROW_ID).addColumn(CF_NAME, QUALIFIER, Bytes.toBytes("Hello, World!")));
    }

    public static void main(String[] args) throws IOException {
        Configuration config = HBaseConfiguration.create();

        try (Connection connection = ConnectionFactory.createConnection(config); Admin admin = connection.getAdmin()) {
            createTable(admin);

            try (Table table = connection.getTable(TABLE_NAME)) {
                putRow(table);
            }
        }
    }
}
```

Use the HBase REST server

You can use the Apache HBase REST server to interact with the Apache HBase. This is a very good alternative if you do not want to use the Java API. Interactions happen using URLs and the REST API. REST uses HTTP to perform various actions, and this makes it easy to interface with the OpDB using a wide array of programming languages.

You can use the REST server to create, delete tables, and perform other operations that have the REST end-points. You can configure SSL for encryption between the client and the REST server. This helps you to ensure that your operations are secure during data transmission.

Using the REST server enables you access your data across different network boundaries. For example, if you have an operational database Data Hub cluster running inside a private network and don't want to expose it to your company's public network, the REST server can work as a gateway between the private and public networks.

Installing the REST Server using Cloudera Manager

You can use the HBase REST API to interact with HBase services, tables, and regions using HTTP endpoints. You must manually install the REST Server only in a CDP Private Cloud Base deployment. The REST Server service is automatically added to the Data Hub cluster in a CDP Public Cloud deployment.

About this task

Install the REST Server using Cloudera Manager in your CDP Private Cloud Base deployment.

Procedure

1. Click the Clusters tab.
2. Select Clusters *HBASE*.
3. Click the Instances tab.
4. Click Add Role Instance.
5. Under HBase REST Server, click Select Hosts.
6. Select one or more hosts to serve the HBase Rest Server role. Click Continue.
7. Select the HBase Rest Server roles. Click Actions For Selected Start.

Using the REST API

The HBase REST Server exposes endpoints that provide CRUD (create, read, update, delete) operations for each HBase process, as well as tables, regions, and namespaces.

For a given endpoint, the HTTP verb controls the type of operation (create, read, update, or delete).

**Note:** curl Command Examples

The examples in these tables use the curl command, and follow these guidelines:

- The HTTP verb is specified using the -X parameter.
- For GET queries, the Accept header is set to text/xml, which indicates that the client (curl) expects to receive responses formatted in XML. You can set it to application/json to receive JSON responses instead.
- For PUT, POST, and DELETE queries, the Content-Type header should be set only if data is also being sent with the -d parameter. If set, it should match the format of the data being sent, to enable the REST server to deserialize the data correctly.
- If you are using a Data Hub cluster, you must provide the basic authentication parameters in your REST query string to access the REST server end-point. For example, `curl -vi -X GET \`
`-H "Accept: text/xml" -u "<USER>:<MY_WORKLOAD_PASSWORD>" \`

For more details about the curl command, see the documentation for the curl version that ships with your operating system.

In CDP, all REST queries are routed through the Apache Knox gateway. In your REST query, ensure that the hostname points to the gateway node and cdp-proxy-api endpoint as shown in these examples.

Table 1: Cluster-Wide Endpoints

Endpoint	HTTP Verb	Description	Example
/version/cluster	GET	Version of HBase running on this cluster	<pre>curl -L -v \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ "https://<gateway_node>/cdp-proxy-api/hbase/version/cluster"</pre>
/status/cluster	GET	Cluster status	<pre>curl -vi -X GET \ -H "Accept: text/xml" \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ "https://<gateway_node>/cdp-proxy-api/hbase/status/cluster"</pre>
/	GET	List of all nonsystem tables	<pre>curl -vi -X GET \ -H "Accept: text/xml" \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ "https://<gateway_node>/cdp-proxy-api/hbase"</pre>

Table 2: Namespace Endpoints

Endpoint	HTTP Verb	Description	Example
/namespaces	GET	List all namespaces.	<pre>curl -vi -X GET \ -H "Accept: text/xml" \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ "https://<gateway_node>/cdp-proxy-api/hbase/namespaces/"</pre>
/namespaces/namespace	GET	Describe a specific namespace.	<pre>curl -vi -X GET \ -H "Accept: text/xml" \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ "https://<gateway_node>/cdp-proxy-api/hbase/namespaces/special_ns"</pre>
/namespaces/namespace	POST	Create a new namespace.	<pre>curl -vi -X POST \ -H "Accept: text/xml" \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ "https://<gateway_node>/cdp-proxy-api/hbase/namespaces/special_ns"</pre>
/namespaces/namespace/tables	GET	List all tables in a specific namespace.	<pre>curl -vi -X GET \ -H "Accept: text/xml" \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ "https://<gateway_node>/cdp-proxy-api/hbase/namespaces/special_ns/tables"</pre>
/namespaces/namespace	PUT	Alter an existing namespace. Currently not used.	<pre>curl -vi -X PUT \ -H "Accept: text/xml" \</pre>

Table 3: Table Endpoints

Endpoint	HTTP Verb	Description	Example
/table/schema	GET	Describe the schema of the specified table.	<pre>curl -vi -X GET \ -H "Accept: text/xml" \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ "https://<gateway_node>/cdp-proxy-api/hbase/users/schema"</pre>
/table/schema	POST	Create a new table, or replace an existing table's schema with the provided schema.	<pre>curl -vi -X POST \ -H "Accept: text/xml" \ -H "Content-Type: text/xml" \ -d '<?xml version="1.0" encoding="UTF-8"?><TableSchema name="users"><ColumnSchema name="cf" /></TableSchema>' \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ "https://<gateway_node>/cdp-proxy-api/hbase/users/schema"</pre>
/table/schema	UPDATE	Update an existing table with the provided schema fragment.	<pre>curl -vi -X PUT \ -H "Accept: text/xml" \ -H "Content-Type: text/xml" \ -d '<?xml version="1.0" encoding="UTF-8"?><TableSchema name="users"><ColumnSchema name="cf" KEEP_DELETED_CELLS="true" /></TableSchema>' \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ "https://<gateway_node>/cdp-proxy-api/hbase/users/schema"</pre>
	15		
/table/schema	DELETE	Delete the table. You must use the table/schema endpoint, not just table/	<pre>curl -vi -X DELETE \</pre>

Table 4: Endpoints for Get Operations

Endpoint	HTTP Verb	Description	Example
/table/row/column:qualifier/timestamp	GET	Get the value of a single row. Values are Base-64 encoded.	Latest version:<pre>curl -vi -X GET \ -H "Accept: text/xml" \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ "https://<gateway_node>/cdp-proxy-api/hbase/users/row1"</pre> Specific timestamp:<pre>curl -vi -X GET \ -H "Accept: text/xml" \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ "https://<gateway_node>/cdp-proxy-api/hbase/users/row1/cf:a/1458586888395"</pre>

Endpoint	HTTP Verb	Description	Example
		Get the value of a single column. Values are Base-64 encoded.	Latest version: <pre>curl -vi -X GET \ -H "Accept: text/xml" \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ "https://<gateway_node>/cdp-proxy-api/hbase/users/row1/cf:a"</pre> Specific version: <pre>curl -vi -X GET \ -H "Accept: text/xml" \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ "https://<gateway_node>/cdp-proxy-api/hbase/users/row1/cf:a"</pre>
/table/row/column:qualifier?v=number_of_versions		Multi-Get a specified number of versions of a given cell. Values are Base-64 encoded.	<pre>curl -vi -X GET \ -H "Accept: text/xml" \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ "https://<gateway_node>/cdp-proxy-api/hbase/users/row1/cf:a?v=2"</pre>

Table 5: Endpoints for Scan Operations

Endpoint	HTTP Verb	Description	Example
/table/scanner/	PUT	Get a Scanner object. Required by all other Scan operations. Adjust the batch parameter to the number of rows the scan should return in a batch. See the next example for adding filters to your Scanner. The scanner endpoint URL is returned as the Location in the HTTP response. The other examples in this table assume that the Scanner endpoint is <code>http://example.com:20550/users/scanner/14586907282437552207</code> .	<pre>curl -vi -X PUT \ -H "Accept: text/xml" \ -H "Content-Type: text/xml" \ -d '<Scanner batch="1"/>' \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ "https://<gateway_node>/cdp-proxy-api/hbase/users/scanner/"</pre>
/table/scanner/	PUT	To supply filters to the Scanner object or configure the Scanner in any other way, you can create a text file and add your filter to the file. For example, to return only rows for which keys start with <code>u123</code> and use a batch size of 100: <pre><Scanner batch="100"> <filter> { "type": "PrefixFilter", "value": "u123" } </filter> </Scanner></pre> Pass the file to the <code>-d</code> argument of the curl request.	<pre>curl -vi -X PUT \ -H "Accept: text/xml" \ -H "Content-Type: text/xml" \ -d @filter.txt \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ "https://<gateway_node>/cdp-proxy-api/hbase/users/scanner/"</pre>
/table/scanner/scanner_id	GET	Get the next batch from the scanner. Cell values are byte-encoded. If the scanner is exhausted, HTTP status 204 is returned.	<pre>curl -vi -X GET \ -H "Accept: text/xml" \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ -u "https://<gateway_node>/cdp-proxy-api/hbase/users/scanner/14586907282437552207"</pre>
/table/scanner/scanner_id	DELETE	Deletes the scanner and frees the resources it was using.	<pre>curl -vi -X DELETE \ -H "Accept: text/xml" \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \</pre>

Table 6: Endpoints for Put Operations

Endpoint	HTTP Verb	Description	Example
/table/row_key/	PUT	Write a row to a table. The row, column qualifier, and value must each be Base-64 encoded. To encode a string, you can use the base64 command-line utility. To decode the string, use base 64 -d. The payload is in the --data argument, so the /users/fakerow value is a placeholder. Insert multiple rows by adding them to the <CellSet> element. You can also save the data to be inserted to a file and pass it to the -d parameter with the syntax -d @filename.txt.	XML: <pre>curl -vi -X PUT \ -H "Accept: text/xml" \ -H "Content-Type: text/xml" \ -d '<?xml version="1.0" encoding="UTF-8" standalone="yes"?><CellSet><Row key="cm93NQo="><Cell column="Y2Y6ZQo=">dmFsdWU1Cg==</Cell></Row></CellSet>' \ -u "<MY_WORKLOAD_USERNAME:MY_WORKLOAD_PASSWORD>" \ "https://<gateway_node>/cdp-proxy-api/hbase/users/FAKEROW"</pre> JSON: <pre>curl -vi -X PUT \ -H "Accept: application/json" \ -H "Content-Type: application/json" \ -d '{"Row":[{"key":"cm93NQo=", "Cell": [{"column":"Y2Y6ZQo=", "\$":"dmFsdWU1Cg==" }]}]}' \</pre>

Using the REST Proxy API

After configuring and starting HBase on your cluster, you can use the HBase REST Proxy API to stream data into HBase, from within another application or shell script, or by using an HTTP client such as wget or curl.

The REST Proxy API is slower than the Java API and may have fewer features. This approach is simple and does not require advanced development experience to implement. However, like the Java and Thrift Proxy APIs, it uses the full write path and can cause compactions and region splits.

Specified addresses without existing data create new values. Specified addresses with existing data create new versions, overwriting an existing version if the row, column:qualifier, and timestamp all match that of the existing value.

```
curl -H "Content-Type: text/xml" http://localhost:8000/test/testrow/test:tes
tcolumn
```

The REST Proxy API does not support writing to HBase clusters that are secured using Kerberos.

For full documentation and more examples, see the [REST Proxy API documentation](#).

Use the Apache Thrift Proxy API

The Apache Thrift library provides cross-language client-server remote procedure calls (RPCs), using *Thrift bindings*.

Prepare Thrift server and client before using Thrift Proxy API

A *Thrift binding* is client code generated by the Apache Thrift Compiler for a target language (such as Python) that allows communication between the Thrift server and clients using that client code. HBase includes an Apache Thrift Proxy API, which allows you to write HBase applications in Python, C, C++, or another language that Thrift supports. The Thrift Proxy API is slower than the Java API and may have fewer features. To use the Thrift Proxy API, you need to configure and run the HBase Thrift server on your cluster. You also need to install the [Apache Thrift compiler](#) on your development system.

After the Thrift server is configured and running, generate *Thrift bindings* for the language of your choice, using an IDL file. An HBase IDL file named HBase.thrift is included as part of HBase. After generating the bindings, copy the Thrift libraries for your language into the same directory as the generated bindings. In the following Python example, these libraries provide the thrift.transport and thrift.protocol libraries. These commands show how you might generate the *Thrift bindings* for Python and copy the libraries on a Linux system.

After installation of the thrift compiler, verify that the thrift compiler version is newer than 0.9.0 by running the `thrift -version` command. You need to find the Hbase.thrift file from the HBase node or copy it to co-locate with the Thrift compiler. Perform the following steps:

```
mkdir HBaseThrift
cd HBaseThrift/
thrift -gen py /path/to/Hbase.thrift
mv gen-py/* .
rm -rf gen-py/
mkdir thrift
cp -rp ~/Downloads/thrift/lib/py/src/* ./thrift/
```

As a result, the HBase thrift Python bindings appears as follows:

```
HbaseThrift/
|-- hbased
|   |-- constants.py
|   |-- Hbase.py
|   |-- Hbase-remote
|   |-- __init__.py
|   |-- ttypes.py
|-- __init__.py
|-- thrift
|   |-- compat.py
|   |-- ext
|       |-- binary.cpp
|       |-- binary.h
|       |-- compact.cpp
|       |-- compact.h
```

```

| | -- endian.h
| | -- module.cpp
| | -- protocol.h
| | -- protocol.tcc
| | -- types.cpp
| | -- types.h
| -- __init__.py
| -- protocol
| | -- __init__.py
| | -- TBase.py
| | -- TBinaryProtocol.py
| | -- TCompactProtocol.py
| | -- THeaderProtocol.py
| | -- TJSONProtocol.py
| | -- TMultiplexedProtocol.py
| | -- TProtocolDecorator.py
| | -- TProtocol.py
| -- server
| | -- __init__.py
| | -- THttpServer.py
| | -- TNonblockingServer.py
| | -- TProcessPoolServer.py
| | -- TServer.py
| -- Thrift.py
| -- TMultiplexedProcessor.py
| -- transport
| | -- __init__.py
| | -- sslcompat.py
| | -- THeaderTransport.py
| | -- THttpClient.py
| | -- TSocket.py
| | -- TSSLSocket.py
| | -- TTransport.py
| | -- TTwisted.py
| | -- TZlibTransport.py
| -- TRecursive.py
| -- TCons.py
| -- TSerialization.py
| -- TTornado.py

```

Introduction to example codes

Choose the right class and functions along with the right configurations for HBase.

Classes and functions

- Transport level: TBufferedTransport, TFramedTransport, TSaslTransport, and THttpClient.
- Protocol level: TBinaryProtocol and TCompactProtocol.

Configurations for HBase thrift

HBase thrift configurations

Property	Default value (secured)	Default value (unsecured)	Description
hbase.thrift.support.proxyuser	true	true	Use this to allow proxy users on the thrift gateway, which is mainly needed for doAs functionality.

Property	Default value (secured)	Default value (unsecured)	Description
hbase.regionserver.thrift.framed	true	true	Use framed transport. When using the THTS or TNonblockingServer, framed transport is always used irrespective of this configuration value.
hbase.regionserver.thrift.compact	true	true	Use the TCompactProtocol instead of the default TBinaryProtocol. TCompactProtocol is a binary protocol that is more compact than the default and typically more efficient.
hbase.regionserver.thrift.http	true	true	Use this to enable HTTP server usage on thrift, which is mainly needed for doAS functionality.
hbase.thrift.security.qop	auth_conf	none	If this is set, HBase Thrift Server authenticates its clients. HBase Proxy User Hosts and Groups must be configured to allow specific users to access HBase through Thrift Server.
hbase.thrift.ssl.enabled	true	false	Encrypt communication between clients and HBase Thrift Server over HTTP using Transport Layer Security (TLS) (formerly known as Secure Socket Layer (SSL)).

Example-1 THttpClient in Secure Cluster

Let us consider that the cluster is secured with the configuration properties mentioned in the *HBase thrift configurations* table under the *Default value (secured)* column.

Before proceeding, ensure that the following applications are installed on your system.

- python 3.6.8 and python 3-devel
- pip 21.3.1
- virtualenv 20.17.1

Perform the following steps:

1. Install virtualenv using pip3.

```
pip3 install virtualenv
```

2. Create a new virtual environment named *PY3ENV*.

```
virtualenv py3env
```

3. Activate the virtual environment.

```
source py3env/bin/activate
```

4. Install the required Python packages and their specific versions. Consider you are inside the python3 virtual environment.

```
pip3 install kerberos==1.3.1 pure-sasl==0.6.2 setuptools==59.6.0 six==1.16.0 wheel==0.37.1
```

This ensures that you have all the necessary dependencies and packages installed to proceed with your project.

```

from thrift.transport import THttpClient
from thrift.protocol import TBinaryProtocol
from hbase.Hbase import Client
from subprocess import call
import ssl
import kerberos
import os

# Get the env parameters
def get_env_params():
    # Replace with your own parameters
    hostname='your_hbase_thrift_hostname'
    cert_file="your_cert_file"
    key_file="your_key_file"
    ca_file="your_ca_file"
    key_pw='your_key_pw'
    keytab_file='your_keytab'
    principal = 'your_principal'
    return hostname, cert_file, key_file, ca_file, keytab_file, principal, key_pw

# Check if a valid Kerberos ticket is already present in the cache
def check_kerberos_ticket():
    ccache_file = os.getenv('KRB5CCNAME')
    if ccache_file:
        ccache = CCache.load_ccache(ccache_file)
        if ccache.get_principal() and not ccache.get_principal().is_anonymous():
            return True
    return False

# Obtain a Kerberos ticket by running kinit from keytab
def kinit(keytab_file, principal):
    call(['kinit', '-kt', keytab_file, principal])
# Authenticate with Kerberos
def kerberos_auth():
    __, krb_context = kerberos.authGSSClientInit("HTTP")
    kerberos.authGSSClientStep(krb_context, "")
    negotiate_details = kerberos.authGSSClientResponse(krb_context)
    headers = {'Authorization': 'Negotiate ' + negotiate_details, 'Content-Type': 'application/binary'}
    return headers

# Initialize an SSL context with certificate verification enabled
def get_ssl_context():
    ssl_context = ssl.create_default_context()
    ssl_context.load_cert_chain(certfile=cert_file, keyfile=key_file, password=key_pw)
    ssl_context.load_verify_locations(cafile=ca_file)
    return ssl_context
if __name__ == '__main__':
    hostname, cert_file, key_file, ca_file, keytab_file, principal, key_pw = get_env_params()
    # Check if a valid Kerberos ticket is not in the cache, then kinit.
    if not check_kerberos_ticket():
        kinit(keytab_file, principal)

# create a THttpClient instance with the SSL context and custom headers
    httpClient = THttpClient.THttpClient('https://' + hostname + ':9090/', ssl_context=get_ssl_context())
    httpClient.setCustomHeaders(headers=kerberos_auth())

```

```
# Initialize TBinaryProtocol with THttpClient
protocol = TBinaryProtocol.TBinaryProtocol(httpClient)

# Create HBase client
client = Client(protocol)
# Retrieve list of HBase tables
tables = client.getTableNames()
print(tables)
# Close connection
httpClient.close()
```

Example-2 THttpClient in Unsecure Cluster

Let us consider that the cluster is unsecured with the configuration properties mentioned in the *HBase thrift configurations* table under the *Default value (unsecured)* column.

```
from thrift.transport import THttpClient
from thrift.protocol import TBinaryProtocol
from hbase.Hbase import Client
# Replace with your own parameters
hostname = 'your_hbase_thrift_server_hostname'

# Initialize THttpClient
httpClient = THttpClient.THttpClient('http://' + hostname + ':9090/')

# Initialize TBinaryProtocol with THttpClient
protocol = TBinaryProtocol.TBinaryProtocol(httpClient)

# Create HBase client
client = Client(protocol)

# Retrieve list of HBase tables
tables = client.getTableNames()
print(tables)

# Close connection
httpClient.close()
```

Example-3 TSaslClientTransport in Secure Cluster without HTTP

If you do not use `THttpClient` and want to use `TSaslClientTransport` for legacy compatibility reasons, ensure that you set `hbase.regionserver.thrift.http` property to `false`. The other settings could be same as the configuration properties mentioned in the *HBase thrift configurations* table under the *Default value (secured)* column.

```
from thrift.transport import TSocket
from thrift.transport import TTransport
from thrift.protocol import TBinaryProtocol
from thrift.protocol import TCompactProtocol
from hbase import Hbase

'''
Assume you already kinit the hbase principal, or you can use the function
in example-1 to kinit.
'''

# Replace with your own parameters
thrift_host = 'your_hbase_thrift_server_hostname'
thrift_port = 9090

# Initialize TSocket and TTransport
socket = TSocket.TSocket(thrift_host, thrift_port)
```

```
transport=TTransport.TSaslClientTransport(socket,host=thrift_host,service='hbase',mechanism='GSSAPI')

# Initialize TCompactProtocol with TTransport
protocol = TCompactProtocol.TCompactProtocol(transport)

# Create HBase client
client = Hbase.Client(protocol)

# Open connection and retrieve list of HBase tables
transport.open()
tables = client.getTableNames()
print(tables)

# Close connection
transport.close()
```

Cloudera recommends you to use the HTTP options (Example-1 and Example-2). You can consider the Example-3 for legacy compatibility issues where some old applications might not rewrite the codes. This is because Hue is using HTTP mode to interact with HBase thrift, and if you disable the HTTP mode, Hue might not work properly with HBase.

Known bugs while using TSaslClientTransport with Kerberos enabled CDP versions

Upstream JIRA [HBASE-21652](#), where a bug is introduced related to Kerberos principal handling. The affected versions are CDP 7.1.6 and earlier. The versions containing the fix are 7.1.7, 7.2.11, and later.

Related Information

[Using the HBase Thrift Interface, Part 1](#)

[Using the HBase Thrift Interface, Part 2](#)

[Python interaction with HBase Thrift proxy in Secured Cluster](#)

[Apache Thrift document](#)

Use the Hue HBase app

Hue includes an HBase App that allows you to interact with HBase through a Thrift proxy server.

Because Hue sits between the Thrift server and the client, the Thrift server assumes that all HBase operations come from the hue user and not the client. To ensure that users in Hue are only allowed to perform HBase operations assigned to their own credentials, and not those of the hue user, you must enable HBase impersonation. For more information about the how to enable doAs Impersonation for the HBase Browser Application, see [Enabling the HBase Browser Application with doAs Impersonation](#).