

Integrating Apache Hive with Spark and BI

Date published: 2019-08-21

Date modified: 2021-04-28



Legal Notice

© Cloudera Inc. 2025. All rights reserved.

The documentation is and contains Cloudera proprietary information protected by copyright and other intellectual property rights. No license under copyright or any other intellectual property right is granted herein.

Unless otherwise noted, scripts and sample code are licensed under the Apache License, Version 2.0.

Copyright information for Cloudera software may be found within the documentation accompanying each component in a particular release.

Cloudera software includes software from various open source or other third party projects, and may be released under the Apache Software License 2.0 (“ASLv2”), the Affero General Public License version 3 (AGPLv3), or other license terms. Other software included may be released under the terms of alternative open source licenses. Please review the license and notice files accompanying the software for additional licensing information.

Please visit the Cloudera software product page for more information on Cloudera software. For more information on Cloudera support services, please visit either the Support or Sales page. Feel free to contact us directly to discuss your specific needs.

Cloudera reserves the right to change any products at any time, and without notice. Cloudera assumes no responsibility nor liability arising from the use of products, except as expressly agreed to in writing by Cloudera.

Cloudera, Cloudera Altus, HUE, Impala, Cloudera Impala, and other Cloudera marks are registered or unregistered trademarks in the United States and other countries. All other trademarks are the property of their respective owners.

Disclaimer: EXCEPT AS EXPRESSLY PROVIDED IN A WRITTEN AGREEMENT WITH CLOUDERA, CLOUDERA DOES NOT MAKE NOR GIVE ANY REPRESENTATION, WARRANTY, NOR COVENANT OF ANY KIND, WHETHER EXPRESS OR IMPLIED, IN CONNECTION WITH CLOUDERA TECHNOLOGY OR RELATED SUPPORT PROVIDED IN CONNECTION THEREWITH. CLOUDERA DOES NOT WARRANT THAT CLOUDERA PRODUCTS NOR SOFTWARE WILL OPERATE UNINTERRUPTED NOR THAT IT WILL BE FREE FROM DEFECTS NOR ERRORS, THAT IT WILL PROTECT YOUR DATA FROM LOSS, CORRUPTION NOR UNAVAILABILITY, NOR THAT IT WILL MEET ALL OF CUSTOMER’S BUSINESS REQUIREMENTS. WITHOUT LIMITING THE FOREGOING, AND TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, CLOUDERA EXPRESSLY DISCLAIMS ANY AND ALL IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, QUALITY, NON-INFRINGEMENT, TITLE, AND FITNESS FOR A PARTICULAR PURPOSE AND ANY REPRESENTATION, WARRANTY, OR COVENANT BASED ON COURSE OF DEALING OR USAGE IN TRADE.

Contents

Introduction to HWC.....	4
Getting started with HWC.....	4
HWC limitations.....	9
Reading data through HWC.....	9
Example of configuring and reading a Hive managed table.....	10
Direct Reader mode introduction.....	11
Using Direct Reader mode.....	12
Direct Reader configuration properties.....	13
Direct Reader limitations.....	14
JDBC read mode introduction.....	14
Using JDBC read mode.....	16
JDBC mode configuration properties.....	17
JDBC mode limitations.....	17
Kerberos configurations for HWC.....	17
Writing data through HWC.....	18
Introduction to HWC and DataFrame APIs.....	19
HWC and DataFrame API limitations.....	21
HWC supported types mapping.....	22
Catalog operations.....	23
Read and write operations.....	23
Commit transaction for Direct Reader.....	25
Close HiveWarehouseSession operations.....	25
Use HWC for streaming.....	26
HWC API Examples.....	26
Hive Warehouse Connector Interfaces.....	27
Submit a Scala or Java application.....	29
HWC integration pyspark, sparklyr, and Zeppelin.....	30
Submit a Python app.....	30
Reading and writing Hive tables in R.....	31
Livy interpreter configuration.....	34
Read and write Hive tables in Zeppelin.....	34
 Apache Hive-Kafka integration.....	 36
Create a table for a Kafka stream.....	36
Querying Kafka data.....	37
Query live data from Kafka.....	38
Perform ETL by ingesting data from Kafka into Hive.....	39
Writing data to Kafka.....	40
Write transformed Hive data to Kafka.....	41
Set consumer and producer properties as table properties.....	41
Kafka storage handler and table properties.....	41
 Connecting Hive to BI tools using a JDBC/ODBC driver.....	 43
Getting the JDBC or ODBC driver in Data Hub.....	44
Integrating Hive and a BI tool.....	44

Introduction to HWC

HWC securely accesses Hive managed tables from Spark. You need to use Hive Warehouse Connector (HWC) software to query Apache Hive managed tables from Apache Spark.

To read Hive external tables from Spark, you do not need HWC. Spark uses native Spark to read external tables. If you configure HWC to work with managed tables, you can use the same configuration to work with external tables. However, you must know that accessing external tables through HWC is slower as compared to accessing external tables through native Spark libraries.

Supported applications and operations

The Hive Warehouse Connector supports the following applications:

- Spark shell
- PySpark
- The spark-submit script
- sparklyr
- Zeppelin with the Livy interpreter

The following list describes a few of the operations supported by the Hive Warehouse Connector:

- Describing a table
- Creating a table in ORC using `.createTable()` or in any format using `.executeUpdate()`
- Writing to a table in ORC format
- Selecting Hive data and retrieving a `DataFrame`
- Writing a `DataFrame` to a Hive-managed ORC table in batch
- Executing a Hive update statement
- Reading table data, transforming it in Spark, and writing it to a new Hive table
- Writing a `DataFrame` or Spark stream to Hive using `HiveStreaming`
- Partitioning data when writing a `DataFrame`

Related Information

[HMS storage](#)

[Orc vs Parquet](#)

Getting started with HWC

You need to know how to use the Hive Warehouse Connector (HWC) with different programming languages and build systems. You find out where HWC binaries are located in CDP parcels and how a Spark application consumes the binaries.

The examples in this topic assume that you are running CDP version 7.2.9.0-203. Substitute your actual CDP version when you copy examples.

Cloudera artifactory and HWC dependency

To pull the HWC dependency corresponding to a release, use the following artifactory:

```
https://repository.cloudera.com/artifactory/cloudera-repos
```

Use with Maven

To use HWC with maven, define the cloudera artifactory as a repository.

```
<repository>
  <id>cloudera</id>
  <name>cloudera</name>
  <url>https://repository.cloudera.com/artifactory/cloudera-repos</url>
</repository>
```

In the pom.xml of the project, add the dependency as shown in the following example:

```
<dependency>
  <groupId>com.hortonworks.hive</groupId>
  <artifactId>hive-warehouse-connector_2.11</artifactId>
  <version>1.0.0.7.2.9.0-203</version>
  <scope>provided</scope>
</dependency>
```

Use with Sbt

Add the Cloudera and Shibboleth repositories, and the HWC dependency to the build sbt as follows:

```
resolvers += "Cloudera repo" at "https://repository.cloudera.com/artifactory/cloudera-repos",

resolvers += "opensaml Repository" at "https://build.shibboleth.net/nexus/content/repositories/releases",

libraryDependencies += "com.hortonworks.hive" % "hive-warehouse-connector_2.11" % "1.0.0.7.2.9.0-203" % "provided",
```

Dependency scope

Generally, you add HWC dependencies in provided scope unless there is a specific requirement to do otherwise. While running spark application, you can specify the HWC jar present in your distribution using the --jars option to spark-submit or spark-shell.

HWC Binaries in CDP

HWC binaries are located in /opt/cloudera/parcels/CDH/lib/hive_warehouse_connector/. This directory contains HWC jar, a python zip, and the R package. Use these binaries to launch Spark applications in Scala, Java, Python, or R.

The following files are in /opt/cloudera/parcels/CDH/lib/hive_warehouse_connector/.

- hive-warehouse-connector-assembly-1.0.0.7.2.9.0-203.jar
- pyspark_hwc-1.0.0.7.2.9.0-203.zip
- SparklyrHWC-1.0.0.7.2.9.0-203

Working with different languages

You use HWC APIs to perform basic read and write operations. You need to understand how to use HWC APIs with different languages. The following examples show basic capabilities that are covered in detail later in this documentation.

Use with Scala

```
import com.hortonworks.hwc.HiveWarehouseSession
import org.apache.spark.sql.{SaveMode, SparkSession}
```

```

object HWCApp {

  def main(args: Array[String]): Unit = {
    val spark = SparkSession.builder.appName("HWCApp").enableHiveSupport.getOrCreate
    val hwc = HiveWarehouseSession.session(spark).build
    // create sample data
    val tvSeries = createSampleDataDf(spark)
    val tableName = "tv_series"

    hwc.dropTable(tableName, true, true)
    println(s"=====Writing to hive table - $tableName via HWC=====")
    // write to hive table via HWC
    tvSeries.write.format(HiveWarehouseSession.HIVE_WAREHOUSE_CONNECTOR)
      .option("table", tableName)
      .mode(SaveMode.Append).save

    println(s"=====Reading hive table $tableName via HWC=====")
    // Read via HWC
    hwc.sql(s"select * from $tableName").show(truncate = false)

    hwc.close()
    spark.stop
  }

  private def createSampleDataDf(spark: SparkSession) = {
    spark.sql("drop table if exists tv_series_dataset")
    spark.sql("create table tv_series_dataset(id int, name string, genres string, rating double) using orc")
    spark.sql("insert into tv_series_dataset values " +
      "(1, 'Chernobyl', 'Drama|History|Tragedy|Science', 9.4), " +
      "(2, 'Westworld', 'Sci-fi', 8.6), (3, 'Sense8', 'Sci-fi', 8.3), " +
      "(4, 'Person of Interest', 'Drama|Sci-fi', 8.4), " +
      "(5, 'Its okay to not be okay', 'Drama', 8.7), " +
      "(6, 'Daredevil', 'Action|Sci-fi', 8.6), " +
      "(7, 'Money Heist', 'Drama|Thriller', 8.3), " +
      "(8, 'Breaking Bad', 'Crime|Drama', 9.5)")
    spark.sql("select * from tv_series_dataset")
  }
}

```

Use with Java

The following Java code is equivalent to the scala code above.

```

import com.hortonworks.hwc.HiveWarehouseSession
import org.apache.spark.sql.Dataset;
import org.apache.spark.sql.Row;
import org.apache.spark.sql.SaveMode;
import org.apache.spark.sql.SparkSession;

public class HWCApp {
  public static void main(String[] args) {
    SparkSession spark = SparkSession.builder().appName("HWCApp").enableHiveSupport().getOrCreate();
    // HiveWarehouseSession creation
    HiveWarehouseSession hwc = HiveWarehouseBuilder.session(spark).build();
    // create sample data
    Dataset<Row> tvSeries = createSampleDataDf(spark);
    String tableName = "tv_series";
    hwc.dropTable(tableName, true, true);
    System.out.println("=====Writing to hive table - " + tableName + " via HWC=====");
  }
}

```

```
// write data to hive table via HWC
tvSeries.write().format(HiveWarehouseSession.HIVE_WAREHOUSE_CONNECTOR)
    .option("table", tableName)
    .mode(SaveMode.Append).save();

System.out.println("=====Reading hive table - " + tableName + " via
HWC=====");
// read hive table as dataframe using HWC
hwc.sql("select * from " + tableName).show(false);
hwc.close();
spark.stop();
}
private static Dataset<Row> createSampleDataDf(SparkSession spark) {
    spark.sql("drop table if exists tv_series_dataset");
    spark.sql("create table tv_series_dataset(id int, name string, genres st
ring, rating double) using orc");
    spark.sql("insert into tv_series_dataset values " +
        "(1, 'Chernobyl', 'Drama|History|Tragedy|Science', 9.4), " +
        "(2, 'Westworld', 'Sci-fi', 8.6), (3, 'Sense8', 'Sci-fi', 8.3), " +
        "(4, 'Person of Interest', 'Drama|Sci-fi', 8.4), " +
        "(5, 'Its okay to not be okay', 'Drama', 8.7), " +
        "(6, 'Daredevil', 'Action|Sci-fi', 8.6), " +
        "(7, 'Money Heist', 'Drama|Thriller', 8.3), " +
        "(8, 'Breaking Bad', 'Crime|Drama', 9.5)");
    return spark.sql("select * from tv_series_dataset");
}
}
```

Launching a Java or Scala app

After packaging the app in a jar, launch the app using standard Spark syntax for launching applications. Provide HWC jar from the distribution. The Spark application can be launched as follows:

```
spark-submit --jars /opt/cloudera/parcels/CDH/lib/hive_warehouse_connector/h
ive-warehouse-connector-assembly-1.0.0.7.2*.jar \
--class com.cloudera.HWCApp \
...More spark/HWC confs...
...More spark/HWC confs...
/path-to-jar/hwc-app.jar
```

Use with Python

```
from pyspark.sql import SparkSession
from pyspark_llap import HiveWarehouseSession

spark = SparkSession.builder.enableHiveSupport().appName("hwc-app").getOrCreate()
hwc = HiveWarehouseSession.session(spark).build()
tableName = "tv_series"
hwc.dropTable(tableName, True, True)

tvSeries = spark.createDataFrame([
    (1, "Chernobyl", "Drama|History|Tragedy|Science", 9.4),
    (2, "Westworld", "Sci-fi", 8.6),
    (3, "Sense8", "Sci-fi", 8.3),
    (4, "Person of Interest", "Drama|Sci-fi", 8.4),
    (5, "It's okay to not be okay", "Drama", 8.7),
    (6, "Daredevil", "Action|Sci-fi", 8.6),
    (7, "Money Heist", "Drama|Thriller", 8.3),
    (8, "Breaking Bad", "Crime|Drama", 9.5)
], ["id", "name", "genres", "rating"])

print("=====Writing to hive table - " + tableName + " via HWC=====")
```

```
# write to hive table via HWC
tvSeries.write.format(HiveWarehouseSession.HIVE_WAREHOUSE_CONNECTOR).option(
  "table", tableName).mode("append").save()
print("=====Reading hive table - " + tableName + " via HWC=====")
# Read via HWC
hwc.sql("select * from " + tableName).show()

hwc.close()
spark.stop()
```

Launching a Python app

After getting the python code ready, launch it using spark-submit. Provide the HWC jar and HWC python zip as follows:

```
spark-submit --jars /opt/cloudera/parcels/CDH/lib/hive_warehouse_connector/
hive-warehouse-connector-assembly-1.0.0.7.2*.jar \
  --py-files /opt/cloudera/parcels/CDH/lib/hive_warehouse_connector/pyspark_hwc-1.0.0.7.2*.zip \
  ...More spark/HWC confs...
  ...More spark/HWC confs...
  /path-to-python-app/hwc-app.py
```

Use with Sparklyr

You can access Hive tables through R by loading the sparklyr library along with the SparklyrHWC package available in /opt/cloudera/parcels/CDH/lib/hive_warehouse_connector/, which can be used to trigger HWC API's from R.

```
library(sparklyr)
library(SparklyrHWC, lib.loc = c(file.path("<path to SparklyrHWC>")))
#Set env variables
Sys.setenv(SPARK_HOME = "/opt/cloudera/parcels/CDH/lib/spark/")
Sys.setenv(HADOOP_HOME = "/opt/cloudera/parcels/CDH/lib/hadoop")

#Configurations needed to use spark-acid and related configurations.

config <- spark_config()
config$spark.sql.hive.hiveserver2.jdbc.url="jdbc:hive2://<url>:10000/default"
config$spark.datasource.hive.warehouse.user.name="hive"
config$spark.hadoop.hive.metastore.uris="thrift://<url>:9083"
config$spark.sql.extensions="com.hortonworks.spark.sql.rule.Extensions"
config$spark.kryo.registrator="com.qubole.spark.hiveacid.util.HiveAcidKryoRegistrator"
config$spark.datasource.hive.warehouse.read.mode="DIRECT_READER_V1"

#Build HWC session
hs <- build(HiveWarehouseBuilder.session(sc))
#Use database
sparklyr::sdf_sql(sc,"use test")
#Reading a managed table using spark acid direct-reader
intDf <- sparklyr::spark_read_table(sc, 'emp_hwc')
#Converts SparkDataframe to R dataframe
sparklyr::sdf_collect(intDf1)

#Writing into a managed table
#Read first table
intDf <- sparklyr::spark_read_table(sc, 'emp_hwc')
#read second table
intDf1 <- sparklyr::spark_read_table(sc, 'emp_overwrite')
#Commit transaction if read using spark-acid
commitTxn(hs)
#Append the second table, to the first.
```

```
SparklyrHWC::spark_write_table('emp_hwc',intDf1,'append')
#Overwrite the first table with the second table.
SparklyrHWC::spark_write_table('emp_hwc',intDf1,'overwrite')

#Using HWC Api's

#create a table from existing table
SparklyrHWC::executeUpdate(hs,"create table hwc1 as select * from 'emp_hwc
'")
#Execute query
hwcDf <- SparklyrHWC::executeQuery(hs, "select * from hwc1")
#convert into R dataframe.
hwcSdf <- sparklyr::sdf_copy_to(sc, hwcDf)
```

HWC limitations

You need to be aware of HWC limitations, including Kerberos properties that are not allowed, and unsupported operations and connections. These limitations are in addition to Direct Reader mode, JDBC mode, and HWC and DataFrames API limitations.

General HWC limitations are:

- HWC supports reading tables in any format, but currently supports writing tables in ORC format only.
- The spark and livy thrift servers are not supported.
- The Hive Union types are not supported.

Workaround for using the Hive Warehouse Connector with Oozie Spark action

Hive and Spark use different Thrift versions and are incompatible with each other. Upgrading Thrift in Hive is complicated and may not be resolved in the near future. Therefore, Thrift packages are shaded inside the HWC JAR to make Hive Warehouse Connector work with Spark and Oozie Spark action. See the workaround in Cloudera Oozie documentation.

Secured cluster configurations

Set the following configurations in a secured cluster:

- `--conf "spark.security.credentials.hiveserver2.enabled=true"`
- `--conf "spark.sql.hive.hiveserver2.jdbc.url.principal=hive/_HOST@ROOT.HWX.SITE"`

The jdbc url must not contain the jdbc url principal and must be passed as shown here.

Related Information

[Using Hive Warehouse Connector with Oozie Spark Action](#)

[Union Types](#)

Reading data through HWC

You can configure one of the several HWC modes to read Apache Hive managed tables from Apache Spark. You need to know about the modes you can configure for querying Hive from Spark. Examples of how to configure the modes are presented.

About this task

In this release, HWC configuration has been simplified.

You set the following configurations when starting the spark shell:

- `spark.sql.extensions="com.hortonworks.spark.sql.rule.Extensions"`
- `spark.datasource.hive.warehouse.read.mode=<mode>`

where <mode> is one of the following:

- `DIRECT_READER_V1`
- `JDBC_CLUSTER`
- `JDBC_CLIENT`

You can transparently read with HWC in different modes using just `spark.sql("<query>")`. You can specify the mode in the spark-shell when you run Spark SQL commands to query Apache Hive tables from Apache Spark. You can also specify the mode in `configuration/spark-defaults.conf`, or using the `--conf` option in `spark-submit`.

For backward compatibility, configuring `spark.datasource.hive.warehouse.read.mode` is the same as the following configurations.

- `--conf spark.datasource.hive.warehouse.read.jdbc.mode //deprecated`
- `--conf spark.sql.hive.hwc.execution.mode //deprecated`
- `--conf spark.datasource.hive.warehouse.read.via.llap //deprecated`

The old configurations are still supported for backward compatibility, but in a later release, support will end for these configurations and `spark.datasource.hive.warehouse.read.mode` will replace these configurations. HWC gives precedence to new configurations when old and new ones are encountered.

Related Information

[Using Direct Reader mode](#)

[Using JDBC read mode](#)

Example of configuring and reading a Hive managed table

Before you begin

Set Kerberos for HWC.

Procedure

1. Choose a read mode.
2. Start the Spark session using the following configurations.
For example, start the Spark session using Direct Reader and configure for kyro serialization:

```
spark-shell --jars ./hive-warehouse-connector-assembly-1.0.0.7.2.8.0.jar \
--master yarn \
--conf spark.sql.extensions="com.hortonworks.spark.sql.rule.Extensions" \
--conf spark.kryo.registrator=com.qubole.spark.hiveacid.util.HiveAcidKy
roRegistrator \
--conf spark.sql.hive.hiveserver2.jdbc.url="jdbc:hive2://hwc-2.hwc.root.
hwx.site:2181/default;retries=5;serviceDiscoveryMode=zooKeeper;zooKeeper
Namespace=hiveserver2" \
--conf spark.sql.hive.hiveserver2.jdbc.url.principal=hive/_HOST@ROOT.HW
X.SITE \
--conf spark.datasource.hive.warehouse.read.mode=DIRECT_READER_V2
```

For example, start the Spark session using the `JDBC_CLUSTER` option:

```
spark-shell --jars ./hive-warehouse-connector-assembly-1.0.0.7.2.8.0.jar
--master yarn
--conf spark.sql.extensions="com.hortonworks.spark.sql.rule.Extensions"
--conf spark.kryo.registrator=com.qubole.spark.hiveacid.util.HiveAcidKyro
Registrator
```

```
--conf spark.sql.hive.hiveserver2.jdbc.url="jdbc:hive2://hwc-2.hwc.root.hwx.site:2181/default;retries=5;serviceDiscoveryMode=zooKeeper;zooKeeperNamespace=hiveserver2"
--conf spark.sql.hive.hiveserver2.jdbc.url.prinicpal=hive/_HOST@ROOT.HWX.SITE
--conf spark.datasource.hive.warehouse.read.mode=JDBC_CLUSTER
```

You must start the Spark session after setting the Direct Read option, so include the configurations in the launch string.

3. Read Apache Hive managed tables.

For example:

```
scala> sql("select * from managedTable").show
```

Direct Reader mode introduction

Direct Reader mode is a transparent connection that Hive Warehouse Connector (HWC) makes to Apache Hive metastore (HMS) to get transaction information. In Direct Reader mode, Spark reads the data directly from the managed table location using the transaction snapshot. You use this mode if you do not need production-level Ranger authorization. Direct Reader mode does not support Ranger authorization.


Requirements and recommendations

Spark Direct Reader mode requires a connection to Hive metastore. A HiveServer (HS2) connection is not needed.

Spark Direct Reader for reading Hive ACID, transactional tables from Spark is supported for production use. Use Spark Direct Reader mode if your ETL jobs do not require authorization and run as super user.

Component interaction

The following diagram shows component interaction ifor Direct Reader reads.



Related Information

[Using Direct Reader mode](#)

[Using JDBC read mode](#)

Using Direct Reader mode

In a few steps, you configure Apache Spark to connect to the Apache Hive metastore. An example shows how to configure Direct Reader reads while launching the Spark shell.

About this task

This procedure assumes you require serialization and sets `spark.kryo.registrator=com.qubole.spark.hiveacid.util.HiveAcidKryoRegistrator`.

Before you begin

For secure clusters, additional configurations will be needed by spark.

.

Procedure

1. In Cloudera Manager, in **Hosts > Roles**, if Hive Metastore appears in the list of roles, copy the host name or IP address.

You use the host name or IP address in the next step to set the host value.

2. Launch the Spark shell and include the Direct Reader configurations.

For example:

```
spark-shell --jars ./hive-warehouse-connector-assembly-1.0.0.7.2.8.0.jar \
--master yarn \
--conf spark.sql.extensions="com.hortonworks.spark.sql.rule.Extensions" \
--conf spark.kryo.registrator=com.qubole.spark.hiveacid.util.HiveAcidKyroRegistrator \
--conf spark.sql.hive.hiveserver2.jdbc.url="jdbc:hive2://<domain name>:<port>/default;principal=hive/_HOST@ROOT.HWX.SITE;retries=5;serviceDiscoveryMode=zooKeeper;zooKeeperNamespace=hiveserver2"

--conf spark.datasource.hive.warehouse.read.mode=DIRECT_READER_V1
```

3. Read data in table customer.

View data in table customer.

```
scala>
spark.sql("select c_customer_sk, c_customer_id, c_last_name, c_birth_country from customer where c_birth_year=1983 limit 2 ").show()
21/02/08 11:03:31 INFO rule.HWCSwitchRule: using DIRECT_READER_V1 extension for reading
+-----+-----+-----+-----+
|c_customer_sk|c_customer_id|c_last_name|c_birth_country|
+-----+-----+-----+-----+
|          55634|AAAAAAACFJNAAAA|    Campbell|      THAILAND|
|          74213|AAAAAAAF0BCBAAA|    Hudgins|    KYRGYZSTAN|
+-----+-----+-----+-----+
```

Direct Reader configuration properties

You need to know the property names and valid values for configuring Direct Reader mode.

Options

In configuration/spark-defaults.conf, or using the --conf option in spark-submit/spark-shell set the following properties:

Name: `spark.sql.extensions`

Value: `com.hortonworks.spark.sql.rule.Extensions`

Required for using Spark SQL in auto-translate direct reader mode. Set before creating the spark session.

spark.datasource.hive.warehouse.read.mode

`DIRECT_READER_V1` or `DIRECT_READER_V1`

Required for performing Direct Reader reads.

Name: `spark.kryo.registrator`

Value: `com.qubole.spark.hiveacid.util.HiveAcidKyroRegistrator`

Set before the spark session. Required if `serialization = kryo`.

Name: `spark.hadoop.hive.metastore.uris`

Value: `thrift://<host>:<port>`

Hive metastore URI.

Name: `--jars`

Value: HWC jar

Pass the HWC jar to spark-shell or spark-submit using the `--jars` option while launching the application. For example, launch spark-shell as follows.

Example: Launch a spark-shell

```
spark-shell --jars \
/opt/cloudera/parcels/CDH/lib/hive_warehouse_connector/hive-warehouse-c
onnecter-assembly-<version>.jar \
--conf "spark.sql.extensions=com.hortonworks.spark.sql.rule.Extensions"
\
--conf "spark.datasource.hive.warehouse.read.mode=DIRECT_READER_V1
--conf "spark.kryo.registrator=com.qubole.spark.hiveacid.util.HiveAci
dKyroRegistrator" \
--conf "spark.hadoop.hive.metastore.uris=<metastore_uri>"
```

Direct Reader limitations

You must understand the limitations of Direct Reader mode and what functionality is not supported.

Limitations

- You cannot write data using HWC Direct Reader.
- Transaction semantics of Spark RDDs are not ensured when using Spark Direct Reader to read ACID tables.
- Supports only single-table transaction consistency. The direct reader does not guarantee that multiple tables referenced in a query read the same snapshot of data.
- Does not auto-commit transactions submitted by rdd APIs. Explicitly close transactions to release locks.
- Requires read and execute access on the hive-managed table locations.
- Does not support Ranger authorization.

You must configure read access to the HDFS, or other, location for managed tables. You must have Read and Execute permissions on hive warehouse location (`hive.metastore.warehouse.dir`).

- Blocks compaction on open read transactions.

The way Spark handles null and empty strings can cause a discrepancy between metadata and actual data when writing the data read by Spark Direct Reader to a CSV file.

Unsupported functionality

Spark Direct Reader does not support the following functionality:


- Writes
- Streaming inserts
- CTAS statements

JDBC read mode introduction

JDBC read mode is a connection that Hive Warehouse Connector (HWC) makes to HiveServer (HS2) to get transaction information. JDBC read mode is secured through Ranger authorization and supports fine-grained access control, such as column masking. You need to understand how you read Apache Hive tables from Apache Spark through HWC using the JDBC mode. The location where your queries are executed affects configuration. Understanding execution locations and recommendations help you configure JDBC reads for your use case.

Component Interaction

Only one JDBC connection to HiveServer (HS2) is a potential bottleneck in data transfer to Spark. The following diagram shows interaction when you configure HWC in JDBC mode with Hive metastore (HMS), TEZ, and HDFS.



HWC does not use JDBC to write. HWC writes to an intermediate location from Spark, and then executes a LOAD DATA query to write the data. Using HWC to write data is recommended for production.

Configuration

A JDBC read takes place in these locations:

- Driver: Using the Hive JDBC url, connects to Hive and executes the query on the driver side.
- Cluster: From Spark executors, connects to Hive through JDBC and executes the query.

Authorization occurs on the server.

A JDBC read occurs in the client or cluster:

- Client (Driver)

In the client, any failures to connect to HiveServer (HS2) will not be retried.

- Cluster (Executor)--recommended

In the cluster, any failures to connect to HS2 will be retried automatically.

JDBC reads are recommended for production for workloads having a data size of 1GB or less. Larger workloads are not recommended for JDBC reads in production due to slow performance.

Where your queries are executed affects the Kerberos configurations for HWC.

Optimize reads using HWC session APIs

Using the HWC session API, you can use `hive.execute` to execute a fast read. This command processes queries through HWC to perform JDBC or Direct Reader reads.

Using JDBC read mode

In a few steps, you configure Apache Spark to connect to HiveServer (HS2). Examples show how to configure JDBC Cluster and JDBC Client modes while launching the Spark shell.

Before you begin

- Accept the default `spark.datasource.hive.warehouse.load.staging.dir` for the temporary staging location required by HWC.
- In `spark-defaults.conf`, check that `spark.hadoop.hive.zookeeper.quorum` is configured.
- In `spark-defaults.conf`, set Kerberos configurations for HWC, or for an unsecured cluster, set `spark.security.credentials.hiveserver2.enabled=false`.

Procedure

1. Find the HiveServer (HS2) JDBC URL in `/etc/hive/conf.cloudera.HIVE_ON_TEZ-1/beeline-site.xml`. The value of `beeline.hs2.jdbc.url.HIVE_ON_TEZ-1` is the HS2 JDBC URL in this sample file.

```
...
<configuration>
  <property>
    <name>beeline.hs2.jdbc.url.default</name>
    <value>HIVE_ON_TEZ-1</value>
  </property>
  <property>
    <name>beeline.hs2.jdbc.url.HIVE_ON_TEZ-1</name>
    <value>jdbc:hive2://<domain name>:2181/;serviceDiscoveryMode=zooKeeper; \
      zooKeeperNamespace=hiveserver2;retries=5</value>
  </property>
</configuration>
```

2. Launch the Spark shell, including the configuration of the JDBC cluster option, and setting the Spark property to the value of the HS2 JDBC URL.
For example:

```
spark-shell --jars ./hive-warehouse-connector-assembly-1.0.0.7.2.8.0.jar \
--master yarn \
--conf spark.sql.extensions="com.hortonworks.spark.sql.rule.Extensions" \
--conf spark.kryo.registrator=com.qubole.spark.hiveacid.util.HiveAcidKyroRegistrator \
--conf spark.sql.hive.hiveserver2.jdbc.url="jdbc:hive2://hwc-2.hwc.root.hwx.site:2181/default;principal=hive/_HOST@ROOT.HWX.SITE;retries=5;serviceDiscoveryMode=zooKeeper;zooKeeperNamespace=hiveserver2"

--conf spark.datasource.hive.warehouse.read.mode=JDBC_CLUSTER
```

3. Read a hive table.

```
scala> sql("select * from managedTable").show
```

Example of JDBC Client Mode

Procedure

Launch the Spark shell in JDBC client mode.

```
spark-shell --jars ./hive-warehouse-connector-assembly-1.0.0.7.2.8.0.jar \
--master yarn \
--conf spark.sql.extensions="com.hortonworks.spark.sql.rule.Extensions" \
--conf spark.kryo.registrator=com.qubole.spark.hiveacid.util.HiveAcidKyroRegistrator \
```

```
--conf spark.sql.hive.hiveserver2.jdbc.url="jdbc:hive2://hwc-2.hwc.root.hwx.  
site:2181/default;principal=hive/_HOST@ROOT.HWX.SITE;retries=5;serviceDiscov  
eryMode=zooKeeper;zooKeeperNamespace=hiveserver2"  
  
--conf spark.datasource.hive.warehouse.read.mode=JDBC_CLIENT
```

JDBC mode configuration properties

You need to know the property names and valid values for configuring JDBC mode.

In configuration/spark-defaults.conf, or using the --conf option in spark-submit/spark-shell set the following properties:

Name: spark.sql.extensions

Value: com.hortonworks.spark.sql.rule.Extensions

Name: spark.datasource.hive.warehouse.read.mode

Value: JDBC_CLUSTER or JDBC_CLIENT

Configures the driver location.

Name: spark.sql.hive.hiveserver2.jdbc.url

Value:

The JDBC endpoint for HiveServer. For more information, see the Apache Hive Wiki (link below). For Knox, provide the HiveServer, not Knox, endpoint.

Name: spark.datasource.hive.warehouse.load.staging.dir

Value: Temporary staging location required by HWC. Set the value to a file system location where the HWC user has write permission.

Name: spark.hadoop.hive.zookeeper.quorum

JDBC mode limitations

You must understand the limitations of JDBC mode and what functionality is not supported.

Keep the following limitations of JDBC mode in mind:

- JDBC_CLUSTER and JDBC_CLIENT are used for reads only, and are recommended for production workloads of 1 GB or less. With larger workload bottlenecks develop in data transfer to Spark.

Writes through HWC of any size are recommended for production. Writes do not use JDBC mode.

- In JDBC_CLUSTER mode, HWC fails to correctly resolve queries that use the ORDER BY clause when run as hive.sql("<query> "). The query returns unordered rows of data even though the query contains an ORDER BY clause.

Kerberos configurations for HWC

You learn how to configure and which parameters to set for a Kerberos-secure HWC connection for querying the Hive metastore from Spark.

The Hive Warehouse Connector (HWC) must connect to HiveServer (HS2) to execute writes or to execute reads in read modes other than Direct Reader. You need to set the following configuration properties to connect HWC to a Kerberos-enabled HiveServer:

- Property: spark.sql.hive.hiveserver2.jdbc.url.principal

Value: Set this value to the value of "hive.server2.authentication.kerberos.principal".

- Property: spark.security.credentials.hiveserver2.enabled

Value: Set this value to "true".

You do not need to explicitly provide other authentication configurations, such as auth type and principal. When Spark opens a secure connection to Hive metastore, Spark automatically picks the authentication configurations from the `hive-site.xml` that is present on the Spark app classpath. For example, to execute queries in direct reader mode through HWC, Spark opens a secure connection to Hive metastore and this authentication occurs automatically.

You can set the properties using the `spark-submit/spark-shell --conf` option.

Writing data through HWC

A step-by-step procedure walks you through connecting to HiveServer (HS2) to perform batch writes from Spark, which is recommended for production. You configure HWC for the managed table write, launch the Spark session, and write ACID, managed tables to Apache Hive.

Before you begin

- Accept the default `spark.datasource.hive.warehouse.load.staging.dir` for the temporary staging location required by HWC.
- Check that `spark.hadoop.hive.zookeeper.quorum` is configured.
- Set Kerberos configurations for HWC, or for an unsecured cluster, set `spark.security.credentials.hiveserver2.enabled=false`.

About this task

Limitation: Only the ORC format is supported for writes.

The way data is written from HWC is not impacted by the read modes configured for HWC. For write operations, HWC writes to an intermediate location (as defined by the value of config `spark.datasource.hive.warehouse.load.staging.dir`) from Spark, followed by executing a "LOAD DATA" query in hive via JDBC. Exception: writing to dynamic partitions creates and intermediate temporary external table.

Using HWC to write data is recommended for production in CDP.

Procedure

1. Open a terminal window, start the Apache Spark session, and include the URL for HiveServer.

```
spark-shell --jars /opt/cloudera/parcels/CDH/jars/hive-warehouse-connect
or-assembly-<version>.jar \
-- conf spark.sql.hive.hiveserver2.jdbc.url=<JDBC endpoint for HiveServer>
...
```

2. Include in the launch string a configuration of the intermediate location to use as a staging directory.
Example syntax:

```
...
--conf spark.datasource.hive.warehouse.load.staging.dir=<path to directo
ry>
```

3. Write a Hive managed table.
For example, in Scala:

```
import com.hortonworks.hwc.HiveWarehouseSession
import com.hortonworks.hwc.HiveWarehouseSession._

val hive = HiveWarehouseSession.session(spark).build();
hive.setDatabase("tpcds_bin_partitioned_orc_1000");
val df = hive.executeQuery("select * from web_sales");
df.createOrReplaceTempView("web_sales");
hive.setDatabase("testDatabase");
```

```
hive.createTable("newTable").ifNotExists()
  .column("ws_sold_time_sk", "bigint")
  .column("ws_ship_date_sk", "bigint")
  .create();

sql("SELECT ws_sold_time_sk, ws_ship_date_sk FROM web_sales WHERE ws_sold_
time_sk > 80000")
  .write.format(HIVE_WAREHOUSE_CONNECTOR)
  .mode("append")
  .option("table", "newTable")
  .save();
```

HWC internally fires the following query to Hive through JDBC:

```
LOAD DATA INPATH '<spark.datasource.hive.warehouse.load.staging.dir>' INTO
TABLE tpchds_bin_partitioned_orc_1000.newTable
```

4. Write to a statically partitioned, Hive managed table named t1 having two partitioned columns c1 and c2.

```
df.write.format(HIVE_WAREHOUSE_CONNECTOR).mode("append").option("partiti
on", "c1='val1',c2='val2']").option("table", "t1").save();
```

HWC internally fires the following query to Hive through JDBC after writing data to a temporary location.

```
LOAD DATA INPATH '<spark.datasource.hive.warehouse.load.staging.dir>' [O
VERWRITE] INTO TABLE db.t1 PARTITION (c1='val1',c2='val2');
```

5. Write to a dynamically partitioned table named t1 having two partitioned cols c1 and c2.

```
df.write.format(HIVE_WAREHOUSE_CONNECTOR).mode("append").option("partiti
on", "c1='val1',c2").option("table", "t1").save();
```

HWC internally fires the following query to Hive through JDBC after writing data to a temporary location.

```
CREATE TEMPORARY EXTERNAL TABLE db.job_id_table(cols...) STORED AS ORC
LOCATION '<spark.datasource.hive.warehouse.load.staging.dir>';

INSERT INTO TABLE t1 PARTITION (c1='val1',c2) SELECT <cols> FROM db.job
_id_table;
```

where <cols> should have comma separated list of columns in the table with dynamic partition columns being the last in the list and in the same order as the partition definition.

Related Information

[Using Direct Reader mode](#)

[Using JDBC read mode](#)

Introduction to HWC and DataFrame APIs

As an Apache Spark developer, you learn the code constructs for executing Apache Hive queries using the HiveWarehouseSession API. In Spark source code, you see how to create an instance of HiveWarehouseSession. You also learn how to access a Hive ACID table using DataFrames.

Supported APIs

- Spark SQL

Supports built-in Spark SQL query read (only) patterns. Output conforms to built-in spark.sql conventions.

- HWC

Supports HiveWarehouse Session API operations using the HWC sql API.

- DataFrames

Supports accessing a Hive ACID table from Scala, or pySpark, directly using DataFrames. Use the short name HiveAcid. Direct reads and writes from the file are not supported.

Spark SQL Example

```
$ spark-shell <parameters to specify HWC jar and config settings>
scala> sql("select * from managedTable").show
scala> spark.read.table("managedTable").show
```

HWC API Example

```
scala> val hive = com.hortonworks.hwc.HiveWarehouseSession.session(spark
).build()
scala> hive.executeQuery("select * from emp_acid").show
scala> hive.executeQuery("select e.emp_id, e.first_name, d.name department
from emp_acid e join dept_ext d on e.dept_id = d.id").show
```

DataFrames Example

Hive ACID tables are tables in Hive metastore and must be formatted using DataFrames as follows:

Syntax:

```
format("HiveAcid").option("table", "<table name>")
```

Example:

```
scala> val df = spark.read.format("HiveAcid").options(Map("table" -> "de
fault.acidtbl")).load()
scala> df.collect()
```

Import statements and variables

The following string constants are defined by the API:

- HIVE_WAREHOUSE_CONNECTOR
- DATAFRAME_TO_STREAM
- STREAM_TO_STREAM

Assuming spark is running in an existing SparkSession, use this code for imports:

- Scala

```
import com.hortonworks.hwc.HiveWarehouseSession
import com.hortonworks.hwc.HiveWarehouseSession._
val hive = HiveWarehouseSession.session(spark).build()
```

- Java

```
import com.hortonworks.hwc.HiveWarehouseSession;
import static com.hortonworks.hwc.HiveWarehouseSession.*;
HiveWarehouseSession hive = HiveWarehouseSession.session(spark).build();
```

- Python

```
from pyspark_llap import HiveWarehouseSession
```

```
hive = HiveWarehouseSession.session(spark).build()
```

Executing queries

HWC supports three methods for executing queries:

- `.sql()`
 - Executes queries in any HWC mode.
 - Consistent with the Spark sql interface.
 - Masks the internal implementation based on the cluster type you configured, either `JDBC_CLIENT` or `JDBC_CLUSTER`.
- `.execute()`
 - Required for executing queries if `spark.datasource.hive.warehouse.read.mode=JDBC_CLUSTER`.
 - Uses a driver side JDBC connection.
 - Provided for backward compatibility where the method defaults to reading in JDBC client mode irrespective of the value of JDBC client or cluster mode configuration.
 - Recommended for catalog queries.
- `.executeQuery()`
 - Executes queries, except catalog queries, in LLAP mode (`spark.datasource.hive.warehouse.read.via.llap= true`)
 - If LLAP is not enabled in the cluster, `.executeQuery()` does not work. CDP Data Center does not support LLAP.
 - Provided for backward compatibility.

Results are returned as a `DataFrame` to Spark.

hive.sql vs. spark.sql

There are a number of important differences between the `hive.sql` and `spark.sql` functions:

- `hive.sql()` can only handle Apache Hive tables.
- `spark.sql()` selects HWC when you query an Apache Hive managed (ACID) table and falls back to built-in Spark for reading external tables.
- You can use the same Spark APIs, such as `spark.sql()`, to access either managed or external tables or temporary views. This is not the case with `hive.sql()`.
- The Direct Reader imposes the constraint that the Hive table must be transactional.

Related Information

[HMS storage](#)

[Orc vs Parquet](#)

HWC and DataFrame API limitations

These limitations are in addition to Direct Reader mode, JDBC mode, and HWC and DataFrames API limitations.

- Table stats (basic stats and column stats) are not generated when you write a `DataFrame` to Hive.
- When the HWC API save mode is `overwrite`, writes are limited.

You cannot read from and overwrite the same table. If your query accesses only one table and you try to overwrite that table using an HWC API write method, a deadlock state might occur. Do not attempt this operation.

Example: Operation Not Supported

```
scala> val df = hive.executeQuery("select * from t1")
scala> df.write.format("com.hortonworks.spark.sql.hive.llap.HiveWarehouseC
onnector"). \
mode("overwrite").option("table", "t1").save
```

HWC supported types mapping

To create HWC API apps, you must know how Hive Warehouse Connector maps Apache Hive types to Apache Spark types, and vice versa. Awareness of a few unsupported types helps you avoid problems.

Spark-Hive supported types mapping

The following types are supported by the HiveWareHouseConnector library:

Spark Type	Hive Type
ByteType	TinyInt
ShortType	SmallInt
IntegerType	Integer
LongType	BigInt
FloatType	Float
DoubleType	Double
DecimalType	Decimal
StringType*	String, Varchar*
BinaryType	Binary
BooleanType	Boolean
TimestampType**	Timestamp**
DateType	Date
ArrayType	Array
StructType	Struct

Notes:

* StringType (Spark) and String, Varchar (Hive)

A Hive String or Varchar column is converted to a Spark StringType column. When a Spark StringType column has maxLength metadata, it is converted to a Hive Varchar column; otherwise, it is converted to a Hive String column.

** Timestamp (Hive)

The Hive Timestamp column loses submicrosecond precision when converted to a Spark TimestampType column because a Spark TimestampType column has microsecond precision, while a Hive Timestamp column has nanosecond precision.

Hive timestamps are interpreted as UTC. When reading data from Hive, timestamps are adjusted according to the local timezone of the Spark session. For example, if Spark is running in the America/New_York timezone, a Hive timestamp 2018-06-21 09:00:00 is imported into Spark as 2018-06-21 05:00:00 due to the 4-hour time difference between America/New_York and UTC.

Spark-Hive unsupported types

Spark Type	Hive Type
CalendarIntervalType	Interval
N/A	Char
MapType	Map
N/A	Union
NullType	N/A
TimestampType	Timestamp With Timezone

Related Information

[HMS storage](#)

Catalog operations

Short descriptions and the syntax of catalog operations, which include creating, dropping, and describing an Apache Hive database and table from Apache Spark, helps you write HWC API apps.

Methods

Three methods of executing catalog operations are supported: `.sql` (recommended), `.execute()` (`spark.datasource.hive.warehouse.read.mode=JDBC_CLIENT`), or `.executeQuery()` for backward compatibility for LLAP reads.

- Set the current database for unqualified Hive table references

```
hive.setDatabase(<database>)
```

- Run a catalog operation and return a DataFrame

```
hive.execute("describe extended web_sales").show()
```

- Show databases

```
hive.showDatabases().show(100)
```

- Show tables for the current database

```
hive.showTables().show(100)
```

- Describe a table

```
hive.describeTable(<table_name>).show(100)
```

- Create a database

```
hive.createDatabase(<database_name>, <ifNotExists>)
```

- Create an ORC table

```
hive.createTable("web_sales").ifNotExists().column("sold_time_sk", "bigint").column("ws_ship_date_sk", "bigint").create()
```

See the `CreateTableBuilder` interface section below for additional table creation options. You can also create Hive tables using `hive.executeUpdate`.

- Drop a database

```
hive.dropDatabase(<databaseName>, <ifExists>, <useCascade>)
```

- Drop a table

```
hive.dropTable(<tableName>, <ifExists>, <usePurge>)
```

Related Information

[HMS storage](#)

Read and write operations

Brief descriptions of HWC API operations and examples cover how to read and write Apache Hive tables from Apache Spark. You learn how to update statements and write DataFrames to partitioned Hive tables, perform batch writes, and use `HiveStreaming`.

Read operations

Run a Hive `SELECT` query and return a DataFrame.

```
hive.sql("select * from web_sales")
```

HWC supports push-downs of DataFrame filters and projections applied to `.sql()`.

Alternatively, you can use `.execute` or `.executeQuery` as previously described.

Run a Hive update statement

Run CREATE, UPDATE, DELETE, INSERT, and MERGE statements in this way:

```
hive.executeUpdate("ALTER TABLE old_name RENAME TO new_name")
```

Write a DataFrame to Hive in batch

This operation uses LOAD DATA INTO TABLE.

Java/Scala:

```
df.write.format(HIVE_WAREHOUSE_CONNECTOR).option("table", <tableName>).save()
```

Python:

```
df.write.format(HiveWarehouseSession().HIVE_WAREHOUSE_CONNECTOR).option("table", &tableName>).save()
```

Write a DataFrame to Hive, specifying partitions

HWC follows Hive semantics for overwriting data with and without partitions and is not affected by the setting of `spark.sql.sources.partitionOverwriteMode` to static or dynamic. This behavior mimics the latest Spark Community trend reflected in Spark-20236 (link below).

Java/Scala:

```
df.write.format(HIVE_WAREHOUSE_CONNECTOR).option("table", <tableName>).option("partition", <partition_spec>).save()
```

Python:

```
df.write.format(HiveWarehouseSession().HIVE_WAREHOUSE_CONNECTOR).option("table", &tableName>).option("partition", <partition_spec>).save()
```

Where `<partition_spec>` is in one of the following forms:

- `option("partition", "c1='val1',c2=val2")` // static
- `option("partition", "c1='val1',c2")` // static followed by dynamic
- `option("partition", "c1,c2")` // dynamic

Depending on the partition spec, HWC generates queries in one of the following forms for writing data to Hive.

- No partitions specified = LOAD DATA
- Only static partitions specified = LOAD DATA...PARTITION
- Some dynamic partition present = CREATE TEMP TABLE + INSERT INTO/OVERWRITE query.

Note: Writing static partitions is faster than writing dynamic partitions.

Write a DataFrame to Hive using HiveStreaming

When using HiveStreaming to write a DataFrame to Hive or a Spark Stream to Hive, you need to escape any commas in the stream, as shown in Use the Hive Warehouse Connector for Streaming (link below).

Java/Scala:

```
//Using dynamic partitioning
df.write.format(DATAFRAME_TO_STREAM).option("table", <tableName>).save()

//Or, writing to a static partition
```

```
df.write.format(DATAFRAME_TO_STREAM).option("table", <tableName>).option("partition", <partition>).save()
```

Python:

```
//Using dynamic partitioning
df.write.format(HiveWarehouseSession().DATAFRAME_TO_STREAM).option("table",
    <tableName>).save()

//Or, writing to a static partition
df.write.format(HiveWarehouseSession().DATAFRAME_TO_STREAM).option("table",
    <tableName>).option("partition", <partition>).save()
```

Write a Spark Stream to Hive using HiveStreaming

Java/Scala:

```
stream.writeStream.format(STREAM_TO_STREAM).option("table", "web_sales").start()
```

Python:

```
stream.writeStream.format(HiveWarehouseSession().STREAM_TO_STREAM).option("table", "web_sales").start()
```

Related Information

[HMS storage](#)

[SPARK-20236](#)

Commit transaction for Direct Reader

For Direct Reader operations, you need to know how to commit or abort transactions.

About this task

A sql listener normally handles this task automatically when a dataframe operation or spark sql query finishes. In some cases when `.explain()`, `.rdd()`, or `.cache()` are invoked on a dataframe, the transaction is not automatically closed. In Spark Direct Reader mode, commit or abort a transaction as follows:

```
scala> com.qubole.spark.hiveacid.transaction.HiveAcidTxnManagerObject.commitTxn(spark)
scala> hive.commitTxn
```

Or, if you are using Hive Warehouse Connector with Direct Reader Mode enabled, you can invoke following API to commit transaction:

```
scala> hive.commitTxn
```

Close HiveWarehouseSession operations

You need to know how to release locks that Apache Spark operations puts on Apache Hive resources. An example shows how and when to release these locks.

About this task

Spark can invoke operations, such as `cache()`, `persist()`, and `rdd()`, on a DataFrame you obtain from running a `HiveWarehouseSession.table()` or `.sql()` (or alternatively, `.execute()` or `.executeQuery()`). The Spark operations can lock Hive resources. You can release any locks and resources by calling the `HiveWarehouseSession.close()`.

Calling `close()` invalidates the `HiveWarehouseSession` instance and you cannot perform any further operations on the instance.

Procedure

Call `close()` when you finish running all other operations on the instance of `HiveWarehouseSession`.

```
import com.hortonworks.hwc.HiveWarehouseSession
import com.hortonworks.hwc.HiveWarehouseSession._
val hive = HiveWarehouseSession.session(spark).build()
hive.setDatabase("tpcds_bin_partitioned_orc_1000")
val df = hive.sql("select * from web_sales")
. . . //Any other operations
.close()
```

You can also call `close()` at the end of an iteration if the application is designed to run in a microbatch, or iterative, manner that does not need to share previous states.

No more operations can occur on the `DataFrame` obtained by `table()` or `sql()` (or alternatively, `.execute()` or `.executeQuery()`).

Use HWC for streaming

When using `HiveStreaming` to write a `DataFrame` to Apache Hive or an Apache Spark Stream to Hive, you need to know how to escape any commas in the stream because the Hive Warehouse Connector uses the commas as the field delimiter.

Procedure

Change the value of the default delimiter property `escape.delim` to a backslash that the Hive Warehouse Connector uses to write streams to `mytable`.

```
ALTER TABLE mytable SET TBLPROPERTIES ('escape.delim' = '\\');
```

Related Information

[HMS storage](#)

HWC API Examples

Examples of using the HWC API include how to create the `DataFrame` from any data source and include an option to write the `DataFrame` to an Apache Hive table.

Write a DataFrame from Spark to Hive example

You specify one of the following [Spark SaveMode](#) modes to write a `DataFrame` to Hive:

- Append
- ErrorIfExists
- Ignore
- Overwrite

In Overwrite mode, HWC does not explicitly drop and recreate the table. HWC queries Hive to overwrite an existing table using `LOAD DATA...OVERWRITE` or `INSERT OVERWRITE...`

When you write the `DataFrame`, the Hive Warehouse Connector creates the Hive table if it does not exist.

The following example uses Append mode.

```
df = //Create DataFrame from any source

val hive = com.hortonworks.hwc.HiveWarehouseSession.session(spark).build()
```

```
df.write.format(HIVE_WAREHOUSE_CONNECTOR)
  .mode("append")
  .option("table", "my_Table")
  .save()
```

ETL example (Scala)

Read table data from Hive, transform it in Spark, and write to a new Hive table.

```
import com.hortonworks.hwc.HiveWarehouseSession
import com.hortonworks.hwc.HiveWarehouseSession._
val hive = HiveWarehouseSession.session(spark).build()
hive.setDatabase("tpcds_bin_partitioned_orc_1000")
val df = hive.sql("select * from web_sales")
df.createOrReplaceTempView("web_sales")
hive.setDatabase("testDatabase")
hive.createTable("newTable")
  .ifNotExists()
  .column("ws_sold_time_sk", "bigint")
  .column("ws_ship_date_sk", "bigint")
  .create()
sql("SELECT ws_sold_time_sk, ws_ship_date_sk FROM web_sales WHERE ws_sold_
time_sk > 80000")
.write.format(HIVE_WAREHOUSE_CONNECTOR)
  .mode("append")
  .option("table", "newTable")
  .save()
```

Related Information

[HMS storage](#)

Hive Warehouse Connector Interfaces

The HiveWarehouseSession, CreateTableBuilder, and MergeBuilder interfaces present available HWC operations.

HiveWarehouseSession interface

```
package com.hortonworks.hwc;

public interface HiveWarehouseSession {

  //Execute Hive SELECT query and return DataFrame (recommended)
  Dataset<Row> sql(String sql);
  //Execute Hive SELECT query and return DataFrame in JDBC client mode
  //Execute Hive catalog-browsing operation and return DataFrame
  Dataset<Row> execute(String sql);

  //Execute Hive SELECT query and return DataFrame in LLAP mode (not available
  in this release)
  Dataset<Row> executeQuery(String sql);

  //Execute Hive update statement
  boolean executeUpdate(String sql);

  //Reference a Hive table as a DataFrame
  Dataset<Row> table(String sql);

  //Return the SparkSession attached to this HiveWarehouseSession
  SparkSession session();

  //Set the current database for unqualified Hive table references
  void setDatabase(String name);
```

```

/**
 * Helpers: wrapper functions over execute or executeUpdate
 */

//Helper for show databases
Dataset<Row> showDatabases();

//Helper for show tables
Dataset<Row> showTables();

//Helper for describeTable
Dataset<Row> describeTable(String table);

//Helper for create database
void createDatabase(String database, boolean ifNotExists);

//Helper for create table stored as ORC
CreateTableBuilder createTable(String tableName);

//Helper for drop database
void dropDatabase(String database, boolean ifExists, boolean cascade);

//Helper for drop table
void dropTable(String table, boolean ifExists, boolean purge);

//Helper for merge query
MergeBuilder mergeBuilder();

//Closes the HWC session. Session cannot be reused after being closed.
void close();

// Closes the transaction started by the direct reader. The transaction is
// not committed if user
// uses rdd APIs.
void commitTxn();
}

```

CreateTableBuilder interface

```

package com.hortonworks.hwc;

public interface CreateTableBuilder {

//Silently skip table creation if table name exists
CreateTableBuilder ifNotExists();

//Add a column with the specific name and Hive type
//Use more than once to add multiple columns
CreateTableBuilder column(String name, String type);

//Specify a column as table partition
//Use more than once to specify multiple partitions
CreateTableBuilder partition(String name, String type);

//Add a table property
//Use more than once to add multiple properties
CreateTableBuilder prop(String key, String value);

//Make table bucketed, with given number of buckets and bucket columns
CreateTableBuilder clusterBy(long numBuckets, String ... columns);

```

```
//Creates ORC table in Hive from builder instance
void create();
}
```

MergeBuilder interface

```
package com.hortonworks.hwc;

public interface MergeBuilder {

    //Specify the target table to merge
    MergeBuilder mergeInto(String targetTable, String alias);

    //Specify the source table or expression, such as (select * from some_table)
    // Enclose expression in braces if specified.
    MergeBuilder using(String sourceTableOrExpr, String alias);

    //Specify the condition expression for merging
    MergeBuilder on(String expr);

    //Specify fields to update for rows affected by merge condition and match
    Expr
    MergeBuilder whenMatchedThenUpdate(String matchExpr, String... nameValuePairs);

    //Delete rows affected by the merge condition and matchExpr
    MergeBuilder whenMatchedThenDelete(String matchExpr);

    //Insert rows into target table affected by merge condition and matchExpr
    MergeBuilder whenNotMatchedInsert(String matchExpr, String... values);

    //Execute the merge operation
    void merge();
}
```

Related Information

[HMS storage](#)

Submit a Scala or Java application

A step-by-step procedure shows you how to submit an app based on the HiveWarehouseConnector library to run on Apache Spark Shell.

Procedure

1. Choose a mode, for example JDBC, for your application.
2. Check that you meet the prerequisites for using JDBC read mode and make the HiveServer (HS2) connection as described for using the JDBC read mode.
3. Locate the hive-warehouse-connector-assembly jar in the /hive_warehouse_connector/ directory. For example, find hive-warehouse-connector-assembly-**<version>**.jar in the following location:

```
/opt/cloudera/parcels/CDH/jars
```

4. Add the connector jar and configurations to the app submission using the --jars option. Example syntax:

```
spark-shell --jars <path to jars>/hive_warehouse_connector/hive-warehouse-connector-assembly-<version>.jar \
--conf <configuration properties>
```

5. Add the path to app you wrote based on the HiveWarehouseConnector API.

Example syntax:

```
<path to app>
```

For example:

```
spark-shell --jars /opt/cloudera/parcels/CDH/jars/hive-warehouse-connector-assembly-<version>.jar \
--conf spark.sql.extensions=com.hortonworks.spark.sql.rule.Extensions \
--conf spark.datasource.hive.warehouse.read.mode=JDBC_CLUSTER \
--conf "spark.hadoop.hive.metastore.uris=thrift://172.27.74.137:9083" \
--conf spark.datasource.hive.warehouse.load.staging.dir=<path to directory> \
/home/myapps/myapp.jar
```

Related Information

[Using Direct Reader mode](#)

[Using JDBC read mode](#)

[HMS storage](#)

HWC integration pyspark, sparklyr, and Zeppelin

Submit a Python app

A step-by-step procedure shows you how to submit a Python app based on the HiveWarehouseConnector library by submitting an application, and then adding a Python package.

Procedure

1. Choose a read option, for example LLAP, for your application and check that you meet the configuration requirements, described earlier.
2. Configure a Spark-HiveServer or a Spark-HiveServer Interactive connection, described earlier or, in your app submission include the appropriate --conf in step 4.
3. Locate the hive-warehouse-connector-assembly jar in the /hive_warehouse_connector/ directory. For example, find hive-warehouse-connector-assembly-<version>.jar in the following location:

```
/opt/cloudera/parcels/CDH/jars
```

4. Add the connector jar and configurations to the app submission using the --jars option.

Example syntax:

```
pyspark --jars <path to jars>/hive_warehouse_connector/hive-warehouse-connector-assembly-<version>.jar \
--conf <configuration properties>
```

5. Locate the pyspark_hwc zip package in the /hive_warehouse_connector/ directory.
6. Add the Python package for the connector to the app submission.

Example syntax:

```
--py-files <path>/hive_warehouse_connector/pyspark_hwc-<version>.zip
```

Example submission in JDBC execution mode:

```
pyspark --jars /opt/cloudera/parcels/CDH/jars/hive-warehouse-connector-assembly-<version>.jar
```

```
--conf spark.sql.extensions=com.hortonworks.spark.sql.rule.Extensions \  
--conf spark.datasource.hive.warehouse.read.mode=JDBC_CLUSTER \  
--conf spark.datasource.hive.warehouse.load.staging.dir=<path to directory  
> \  
--py-files /opt/cloudera/parcels/CDH/lib/hive_warehouse_connector/pyspark_hwc-<version>.zip
```

Related Information

[Using Direct Reader mode](#)

[Using JDBC read mode](#)

[HMS storage](#)

Reading and writing Hive tables in R

The Hive Warehouse Connector (HWC) supports reads and writes to Apache Hive managed ACID tables in R. Cloudera provides an R package SparklyrHWC that includes all HWC methods, such as `execute` and `executeQuery`, and a `spark_write_table` method to write to managed tables. The native sparklyr `spark_write_table` method supports writes to external tables only.

Support

HWC should work with Sparklyr 1.0.4. Versions later than 1.0.4 should also work if interfaces are not changed by sparklyr. However, Sparklyr isn't supported by Cloudera. We will support any issues around using HWC from sparklyr.

Downloading SparklyrHWC

You can download the SparklyrHWC R package that includes HWC methods from your CDP Cluster. Go to `/opt/cloudera/parcels/CDH/lib/hive_warehouse_connector/`. Copy the `SparklyrHWC-<version>` to your download location.

About this task

To read and write Hive tables in R, you need to configure an HWC execution mode. You can configure either one of the following HWC execution modes in R:

- JDBC mode
 - Suitable for writing production workloads.
 - Suitable for reading production workloads having a data size of 1 GB or less.
 - Use this mode for reading if latency is not an issue.
- Spark-ACID mode
 - Suitable for reading production workloads.
 - Does not support writes

Reading and writing managed tables

You can read Hive managed tables using either JDBC or Spark-ACID mode. The mode you configure affects the background process. You use the same R code regardless of the mode with one exception: You do not need to call the `commitTxn(hs)` when using JDBC mode.

To write to Hive managed tables, you must connect to HWC in JDBC mode.

Reading and writing external tables

You can read and write Hive external tables in R using the sparklyr package. HWC is not required.

In the following procedure, you configure Spark-Acid execution mode to read tables on a production cluster. You use the native sparklyr `spark_read_table` and `spark_load_table` to read Hive managed tables in R.

Reading a Hive managed table example

Procedure

1. Read tables using spark-acid - direct_reader_v1 mode.

For example:

```
library(sparklyr)

// Configurations needed to use spark-acid
config <- spark_config()
config$sparklyr.jars.default <- "<path to hwc jar>"
config$spark.sql.hive.hiveserver2.jdbc.url="jdbc:hive2://<url>:10000/default"
config$spark.datasource.hive.warehouse.user.name="hive"
config$spark.hadoop.hive.metastore.uris="thrift://<url>:9083"
config$spark.sql.extensions="com.hortonworks.spark.sql.rule.Extensions"
config$spark.kryo.registrator="com.qubole.spark.hiveacid.util.HiveAcidKyroRegistrator"
config$spark.datasource.hive.warehouse.read.mode="DIRECT_READER_V1"

//Set env variables

Sys.setenv(SPARK_HOME = "/opt/cloudera/parcels/CDH/lib/spark/")
Sys.setenv(HADOOP_HOME = "/opt/cloudera/parcels/CDH/lib/hadoop")
// Spark context can be set to local or yarn mode
sc <- spark_connect(master = "local", config = config)
```

2. Read Hive using sparklyr methods spark_read_table() or spark_load_table().

For example:

```
// reading a managed table using spark acid direct-reader

> intDf <- sparklyr::spark_read_table(sc, 'emp_hwc')
> sparklyr::sdf_collect(intDf1) // Converts SparkDataframe to R dataframe
```

3. Explicitly commit your code. For example, use SparklyrHWC::commitTxn(hs), where hs is the HiveWarehouseSessionImpl object.

You need to commit your code using commitTxn() due to sparklyr calling specific cache methods internally.

Writing a Hive managed table in R

About this task

You configure JDBC mode and use SparklyrHWC::spark_write_table() to write to a managed table.

Procedure

1. In R, configure JDBC mode by setting the following configs and values:

```
> config$spark.sql.extensions="com.hortonworks.spark.sql.rule.Extensions"
> config$spark.datasource.hive.warehouse.read.via.llap="false"
> config$spark.datasource.hive.warehouse.read.jdbc.mode="cluster"
```

2. Include the sparklyr library.

```
> library(sparklyr) // Load sparklyr library
```

3. Write to a managed table using SparklyrHWC::spark_write_table.

```
> library(sparklyr) // Load sparklyr library
```

```

> Sys.setenv(HADOOP_HOME = "/opt/cloudera/parcels/CDH/lib/hadoop") // set
environment variables
> Sys.setenv(SPARK_HOME = "/opt/cloudera/parcels/CDH/lib/spark/")
> sc <- spark_connect(master = "yarn", config = config) // Create a spark
Connection.

> intDf <- sparklyr::spark_read_table(sc, 'emp_hwc') // read first table
> intDf1 <- sparklyr::spark_read_table(sc, 'emp_overwrite') // read sec
ond table
> commitTxn(hs) // Commit transaction if read using spark-acid
> SparklyrHWC::spark_write_table('emp_hwc',intDf1,'append') // Append the
second table, to the first.
> SparklyrHWC::spark_write_table('emp_hwc',intDf1,'overwrite') // Overwri
te the first table with the second table.

```

You do not need to call `commitTxn(hs)` when using JDBC mode.

Supported HWC APIs in R

About this task

The `SparklyrHWC` package supports the following HWC APIs in Scala.

- `execute()` and `executeQuery()` (recommended) APIs to run read SQL statements
- `executeUpdate()` API to run write SQL statements
- API call for hive CTASK operations (create table as select)
- Other HWC APIs, such as `dropTable`, `dropDatabase`, `showTable`

Any HWC API in Scala can be used in R. The behavior of these APIs in R and HWC is similar.

Procedure

1. Create a table using another existing table.

```
SparklyrHWC::executeUpdate(hs,"create table hwc1 as select * from hwc")
```

2. Read the new table.

```
hwcDf <- SparklyrHWC::executeQuery(hs, "select * from hwc1")
```

3. Convert the table to a `SparkDataframe`.

```
hwcSdf <- sparklyr::sdf_copy_to(sc, hwcDf)
```

4. Write the table to a new table.

```
SparklyrHWC::spark_write_table('hwcNew',hwcSdf,'OVERWRITE')
```

5. Append the table data to the new table.

```
SparklyrHWC::spark_write_table('hwcNew',hwcSdf,'APPEND')
```

6. Insert data into the table using HWC API.

```
SparklyrHWC::executeUpdate(hs,"insert into hwcNew values(2,'B')")
```

7. Read the newly create table using HWC API.

```
SparklyrHWC::executeQuery(hs, "select * from hwcNew")
```

Livy interpreter configuration

You can use the Hive Warehouse Connector in Zeppelin notebooks with the Livy interpreter by modifying or adding properties to your livy interpreter settings. The Livy interpreter accesses processing engines and data sources from the Zeppelin UI.

Requirements

- Configurations require a livy prefix.
- A reference to the HWC jar on the local file system is required.

Interpreter properties

- livy.spark.hadoop.hive.metastore.uris -
thrift://<domain name>:<port>
Example: thrift://hwc-secure-1.hwc-secure.root.hwx.site:9083
- livy.spark.jars -
local:/opt/cloudera/parcels/<version>/jars/hive-warehouse-connector-assembly-<version>.jar
Example: local:/opt/cloudera/parcels/CDH-7.2.1-1.cdh7.2.1.p0.4847773/jars/hive-warehouse-connector-assembly-1.0.0.7.2.1.0-327.jar
Use the local file ("local:").
- livy.spark.kryo.registrator - com.qubole.spark.hiveacid.util.HiveAcidKyroRegistrator
- livy.spark.security.credentials.hiveserver2.enabled- true
- livy.spark.sql.extensions - com.qubole.spark.hiveacid.HiveAcidAutoConvertExtension
- livy.spark.sql.hive.hiveserver2.jdbc.url -
jdbc:hive2://<domain name>:<port>/
default;retries=5;serviceDiscoveryMode=zooKeeper;zooKeeperNamespace=hiveserver2
Example: jdbc:hive2://hwc-secure-1.hwc-secure.root.hwx.site:2181/
default;retries=5;serviceDiscoveryMode=zooKeeper;zooKeeperNamespace=hiveserver2.
- livy.spark.sql.hive.hiveserver2.jdbc.url.principal - hive/_HOST@ROOT.HWX.SITE

Read and write Hive tables in Zeppelin

You can read and write Hive ACID tables from a Spark application using Zeppelin, a browser-based GUI for interactive data exploration, modeling, and visualization.

Before you begin

You must be running spark application and have all the appropriate permissions to read the data from the hive warehouse directory for managed (ACID) tables.

Procedure

1. Open the livy configuration file on the livy node and configure HWC Spark Direct Reader mode.

```
%livy2.conf
...
livy.spark.hadoop.hive.metastore.uris thrift://hwc-secure-1.hwc-secure.r
oot.hwx.site:9083
livy.spark.jars local:/opt/cloudera/parcels/CDH-7.2.1-1.cdh7.2.1.p0.484777
3/jars/hive-warehouse-connector-assembly-1.0.0.7.2.1.0-327.jar
livy.spark.kryo.registrator com.qubole.spark.hiveacid.util.HiveAcidKyroRe
gistrator
livy.spark.security.credentials.hiveserver2.enabled true
livy.spark.sql.extensions com.qubole.spark.hiveacid.HiveAcidAutoConvertEx
tension
```

```
livy.spark.sql.hive.hiveserver2.jdbc.url jdbc:hive2://hwc-secure-1.hwc-secure.root.hwx.site:2181/default;retries=5;serviceDiscoveryMode=zooKeeper;zooKeeperNamespace=hiveserver2
livy.spark.sql.hive.hiveserver2.jdbc.url.principal hive/_HOST@ROOT.HWX.SITE
...
```

2. In a Zeppelin notebook, read a Hive ACID table.

```
sql("show tables").show
sql("select * from hwc2").show
```

Previous livy session is expired, new livy session is created.

database	tableName	temporary
default	hwc1	false
default	hwc2	false
default	sample_07	false
default	sample_08	false
default	t1	false
default	t2	false
default	t3	false
default	web_logs	false

c1	c2
1	one
2	two

3. Perform a batch write from Spark.

```
val hive = com.hortonworks.hwc.HiveWarehouseSession.session(spark).build()
val df = Seq(
  (1, "a", 1.1),
  (2, "b", 2.2),
  (3, "c", 3.3)
).toDF("col1", "col2", "col3")
val tableName = "t3"
hive.dropTable(tableName, true, true)
```

```
df.write.format("com.hortonworks.spark.sql.hive.llap.HiveWarehouseConnector").mode("append").option("table", tableName).save()
```

4. Read data from table t3.

```
sql("select * from t3").show
```

Output is:

```
tableName: String = t3
+----+----+----+
|col1|col2|col3|
+----+----+----+
|   1|   a|  1.1|
|   2|   b|  2.2|
|   3|   c|  3.3|
+----+----+----+
```

Apache Hive-Kafka integration

As an Apache Hive user, you can connect to, analyze, and transform data in Apache Kafka from Hive. You can offload data from Kafka to the Hive warehouse. Using Hive-Kafka integration, you can perform actions on real-time data and incorporate streamed data into your application.

You connect to Kafka data from Hive by creating an external table that maps to a Kafka topic. The table definition includes a reference to a Kafka storage handler that connects to Kafka. On the external table, Hive-Kafka integration supports ad hoc queries, such as questions about data changes in the stream over a period of time. You can transform Kafka data in the following ways:

- Perform data masking
- Join dimension tables or any stream
- Aggregate data
- Change the SerDe encoding of the original stream
- Create a persistent stream in a Kafka topic

You can achieve data offloading by controlling its position in the stream. The Hive-Kafka connector supports the following serialization and deserialization formats:

- JsonSerializer (default)
- OpenCSVSerde
- AvroSerDe

Related Information

[Apache Kafka Documentation](#)

Create a table for a Kafka stream

You can create an external table in Apache Hive that represents an Apache Kafka stream to query real-time data in Kafka. You use a storage handler and table properties that map the Hive database to a Kafka topic and broker. If the Kafka data is not in JSON format, you alter the table to specify a serializer-deserializer for another format.

Procedure

1. Get the name of the Kafka topic you want to query to use as a table property.
For example: "kafka.topic" = "wiki-hive-topic"

- Construct the Kafka broker connection string.
For example: "kafka.bootstrap.servers"="kafka.hostname.com:9092"
- Create an external table named kafka_table by using 'org.apache.hadoop.hive.kafka.KafkaStorageHandler', as shown in the following example:

```
CREATE EXTERNAL TABLE kafka_table
(`timestamp` timestamp, `page` string, `newPage` boolean,
added int, deleted bigint, delta double)
STORED BY 'org.apache.hadoop.hive.kafka.KafkaStorageHandler'
TBLPROPERTIES
("kafka.topic" = "test-topic", "kafka.bootstrap.servers"="node2:9092");
```

- If the default JSON serializer-deserializer is incompatible with your data, choose another format in one of the following ways:
 - Alter the table to use another supported serializer-deserializer. For example, if your data is in Avro format, use the Kafka serializer-deserializer for Avro:

```
ALTER TABLE kafka_table SET TBLPROPERTIES ("kafka.serde.class"="org.apache.hadoop.hive.serde2.avro.AvroSerDe");
```

- Create an external table that specifies the table in another format. For example, create a table named that specifies the Avro format in the table definition:

```
CREATE EXTERNAL TABLE kafka_t_avro
(`timestamp` timestamp, `page` string, `newPage` boolean,
added int, deleted bigint, delta double)
STORED BY 'org.apache.hadoop.hive.kafka.KafkaStorageHandler'
TBLPROPERTIES
("kafka.topic" = "test-topic",
"kafka.bootstrap.servers"="node2:9092"
-- STORE AS AVRO IN KAFKA
"kafka.serde.class"="org.apache.hadoop.hive.serde2.avro.AvroSerDe");
```

Related Information

[Apache Kafka Documentation](#)

Querying Kafka data


You can get useful information, including Kafka record metadata from a table of Kafka data by using typical Hive queries.

Each Kafka record consists of a user payload key (byte []) and value (byte[]), plus the following metadata fields:

- Partition int32
- Offset int64
- Timestamp int64

The Hive row represents the dual composition of Kafka data:

- The user payload serialized in the value byte array
- The metadata: key byte array, partition, offset, and timestamp fields



In the Hive representation of the Kafka record, the key byte array is called `___key` and is of type binary. You can cast `___key` at query time. Hive appends `___key` to the last column derived from value byte array, and appends the partition, offset, and timestamp to `___key` columns that are named accordingly.

Related Information[Apache Kafka Documentation](#)**Query live data from Kafka**

You can get useful information from a table of Kafka data by running typical queries, such as counting the number of records streamed within an interval of time or defining a view of streamed data over a period of time.

Before you begin

This task requires Kafka 0.11 or later to support time-based lookups and prevent full stream scans.

About this task

This task assumes you created a table named `kafka_table` for a Kafka stream.

Procedure

1. List the table properties and all the partition or offset information for the topic.
`DESCRIBE EXTENDED kafka_table;`
2. Count the number of Kafka records that have timestamps within the past 10 minutes.

```
SELECT COUNT(*) FROM kafka_table
  WHERE `__timestamp` > 1000 * to_unix_timestamp(CURRENT_TIMESTAMP - interval '10' MINUTES);
```

Such a time-based seek requires Kafka 0.11 or later, which has a Kafka broker that supports time-based lookups; otherwise, this query leads to a full stream scan.

3. Define a view of data consumed within the past 15 minutes and mask specific columns.

```
CREATE VIEW last_15_minutes_of_kafka_table AS SELECT `timestamp`, `user`,
  delta,
  ADDED FROM kafka_table
  WHERE `__timestamp` > 1000 * to_unix_timestamp(CURRENT_TIMESTAMP - interval '15' MINUTES) ;
```

4. Create a dimension table.

```
CREATE TABLE user_table (`user` string, `first_name` string , age int, gender string, comments string) STORED as ORC ;
```

5. Join the view of the stream over the past 15 minutes to `user_table`, group by gender, and compute aggregates over metrics from fact table and dimension tables.

```
SELECT SUM(added) AS added, SUM(deleted) AS deleted, AVG(delta) AS delta,
  AVG(age) AS avg_age , gender
  FROM last_15_minutes_of_kafka_table
  JOIN user_table ON `last_15_minutes_of_kafka_table`.`user` = `user_table`.`user`
  GROUP BY gender LIMIT 10;
```

6. Perform a classical user retention analysis over the Kafka stream consisting of a stream-to-stream join that runs adhoc queries on a view defined over the past 15 minutes.

```
-- Stream join over the view itself
-- Assuming l15min_wiki is a view of the last 15 minutes
SELECT COUNT( DISTINCT activity.`user`) AS active_users,
  COUNT(DISTINCT future_activity.`user`) AS retained_users
  FROM l15min_wiki AS activity
  LEFT JOIN l15min_wiki AS future_activity ON activity.`user` = future_activity.`user`
```

```

AND activity.`timestamp` = future_activity.`timestamp` - interval '5' min
utes ;

-- Stream-to-stream join
-- Assuming wiki_kafka_hive is the entire stream.
SELECT floor_hour(activity.`timestamp`), COUNT( DISTINCT activity.`user`)
  AS active_users,
COUNT(DISTINCT future_activity.`user`) as retained_users
FROM wiki_kafka_hive AS activity
LEFT JOIN wiki_kafka_hive AS future_activity ON activity.`user` = future_
activity.`user`
AND activity.`timestamp` = future_activity.`timestamp` - interval '1' ho
ur
GROUP BY floor_hour(activity.`timestamp`);

```

Related Information

[Apache Kafka Documentation](#)

Perform ETL by ingesting data from Kafka into Hive

You can extract, transform, and load a Kafka record into Hive in a single transaction.

Procedure

1. Create a table to represent source Kafka record offsets.

```

CREATE TABLE kafka_table_offsets(partition_id int, max_offset bigint, in
sert_time timestamp);

```

2. Initialize the table.

```

INSERT OVERWRITE TABLE kafka_table_offsets
SELECT `__partition`, min(`__offset`) - 1, CURRENT_TIMESTAMP
FROM wiki_kafka_hive
GROUP BY `__partition`, CURRENT_TIMESTAMP;

```

3. Create the destination table.

```

CREATE TABLE orc_kafka_table (partition_id int, koffset bigint, ktimestamp
bigint,
  `timestamp` timestamp , `page` string, `user` string, `diffurl` string,
  `isrobot` boolean, added int, deleted int, delta bigint
) STORED AS ORC;

```

4. Insert Kafka data into the ORC table.

```

FROM wiki_kafka_hive ktable JOIN kafka_table_offsets offset_table
ON (ktable.`__partition` = offset_table.partition_id
AND ktable.`__offset` > offset_table.max_offset )
INSERT INTO TABLE orc_kafka_table
SELECT `__partition`, `__offset`, `__timestamp`,
  `timestamp`, `page`, `user`, `diffurl`, `isrobot`, added , deleted , del
ta
INSERT OVERWRITE TABLE kafka_table_offsets
SELECT `__partition`, max(`__offset`), CURRENT_TIMESTAMP
GROUP BY `__partition`, CURRENT_TIMESTAMP;

```

5. Check the insertion.

```

SELECT MAX(`koffset`) FROM orc_kafka_table LIMIT 10;

```

```
SELECT COUNT(*) AS c FROM orc_kafka_table
GROUP BY partition_id, koffset HAVING c > 1;
```

6. Repeat step 4 periodically until all the data is loaded into Hive.

Writing data to Kafka

You can extract, transform, and load a Hive table to a Kafka topic for real-time streaming of a large volume of Hive data. You need some understanding of write semantics and the metadata columns required for writing data to Kafka.

Write semantics

The Hive-Kafka connector supports the following write semantics:

- At least once (default)
- Exactly once

At least once (default)

The default semantic. At least once is the most common write semantic used by streaming engines. The internal Kafka producer retries on errors. If a message is not delivered, the exception is raised to the task level, which causes a restart, and more retries. The At least once semantic leads to one of the following conclusions:

- If the job succeeds, each record is guaranteed to be delivered at least once.
- If the job fails, some of the records might be lost and some might not be sent.

In this case, you can retry the query, which eventually leads to the delivery of each record at least once.

Exactly once

Following the exactly once semantic, the Hive job ensures that either every record is delivered exactly once, or nothing is delivered. You can use only Kafka brokers supporting the Transaction API (0.11.0.x or later). To use this semantic, you must set the table property "kafka.write.semantic"="EXACTLY_ONCE".

Metadata columns

In addition to the user row payload, the insert statement must include values for the following extra columns:

__key

Although you can set the value of this metadata column to null, using a meaningful key value to avoid unbalanced partitions is recommended. Any binary value is valid.

__partition

Use null unless you want to route the record to a particular partition. Using a nonexistent partition value results in an error.

__offset

You cannot set this value, which is fixed at -1.

__timestamp

You can set this value to a meaningful timestamp, represented as the number of milliseconds since epoch. Optionally, you can set this value to null or -1, which means that the Kafka broker strategy sets the timestamp column.

Related Information

[Apache Kafka Documentation](#)

Write transformed Hive data to Kafka

You can change streaming data and include the changes in a stream. You extract a Kafka input topic, transform the record in Hive, and load a Hive table back into a Kafka record.

About this task

This task assumes that you already queried live data from Kafka. When you transform the record in the Hive execution engine, you compute a moving average over a window of one minute. The resulting record that you write back to another Kafka topic is named `moving_avg_wiki_kafka_hive`.

.

Procedure

1. Create an external table to represent the Hive data that you want to load into Kafka.

```
CREATE EXTERNAL TABLE moving_avg_wiki_kafka_hive
(`channel` string, `namespace` string, `page` string, `timestamp` timestamp
, avg_delta double )
STORED BY 'org.apache.hadoop.hive.kafka.KafkaStorageHandler'
TBLPROPERTIES
  ("kafka.topic" = "moving_avg_wiki_kafka_hive",
   "kafka.bootstrap.servers"="kafka.hostname.com:9092",
   -- STORE AS AVRO IN KAFKA
   "kafka.serde.class"="org.apache.hadoop.hive.serde2.avro.AvroSerDe");
```

2. Insert data that you select from the Kafka topic back into the Kafka record.

```
INSERT INTO TABLE moving_avg_wiki_kafka_hive
SELECT `channel`, `namespace`, `page`, `timestamp`,
  AVG(delta) OVER (ORDER BY `timestamp` ASC ROWS BETWEEN 60 PRECEDING AND
  CURRENT ROW) AS avg_delta,
  null AS `__key`, null AS `__partition`, -1 AS `__offset`, to_epoch_milli
(CURRENT_TIMESTAMP) AS `__timestamp`
FROM l15min_wiki;
```

The timestamps of the selected data are converted to milliseconds since epoch for clarity.

Related Information

[Query live data from Kafka](#)

Set consumer and producer properties as table properties

You can use Kafka consumer and producer properties in the TBLPROPERTIES clause of a Hive query. By prefixing the key with `kafka.consumer` or `kafka.producer`, you can set the table properties.

Procedure

For example, if you want to inject 5000 poll records into the Kafka consumer, use the following syntax.

```
ALTER TABLE kafka_table SET TBLPROPERTIES ("kafka.consumer.max.poll.records"
="5000");
```

Kafka storage handler and table properties

You use the Kafka storage handler and table properties to specify the query connection and configuration.

Kafka storage handler

You specify 'org.apache.hadoop.hive.kafka.KafkaStorageHandler' in queries to connect to, and transform a Kafka topic into, a Hive table. In the definition of an external table, the storage handler creates a view over a single Kafka topic. For example, to use the storage handler to connect to a topic, the following table definition specifies the storage handler and required table properties: the topic name and broker connection string.

```
CREATE EXTERNAL TABLE kafka_table
  (`timestamp` timestamp, `page` string, `newPage` boolean,
   added int, deleted bigint, delta double)
  STORED BY 'org.apache.hadoop.hive.kafka.KafkaStorageHandler'
  TBLPROPERTIES
    ("kafka.topic" = "test-topic", "kafka.bootstrap.servers"="localhost:90
    92");
```

You set the following table properties for with the Kafka storage handler:

kafka.topic

The Kafka topic to connect to

kafka.bootstrap.servers

The broker connection string

Storage handler-based optimizations

The storage handler can optimize reads using a filter push-down when you run a query such as the following time-based lookup supported on Kafka 0.11 or later:

```
SELECT COUNT(*) FROM kafka_table
  WHERE `__timestamp` > 1000 * to_unix_timestamp(CURRENT_TIMESTAMP - int
  erval '10' MINUTES) ;
```

The Kafka consumer supports seeking on the stream based on an offset, which the storage handler leverages to push down filters over metadata columns. The storage handler in the example above performs seeks based on the Kafka record `__timestamp` to read only recently arrived data.

The following logical operators and predicate operators are supported in the WHERE clause:

Logical operators: OR, AND

Predicate operators: <, <=, >=, >, =

The storage handler reader optimizes seeks by performing partition pruning to go directly to a particular partition offset used in the WHERE clause:

```
SELECT COUNT(*) FROM kafka_table
  WHERE (`__offset` < 10 AND `__offset` > 3 AND `__partition` = 0)
  OR (`__partition` = 0 AND `__offset` < 105 AND `__offset` > 99)
  OR (`__offset` = 109);
```

The storage handler scans partition 0 only, and then read only records between offset 4 and 109.

Kafka metadata

In addition to the user-defined payload schema, the Kafka storage handler appends to the table some additional columns, which you can use to query the Kafka metadata fields:

__key

Kafka record key (byte array)

__partition

Kafka record partition identifier (int 32)

__offset

Kafka record offset (int 64)

__timestamp

Kafka record timestamp (int 64)

The partition identifier, record offset, and record timestamp plus a key-value pair constitute a Kafka record. Because the key-value is a 2-byte array, you must use SerDe classes to transform the array into a set of columns.

Table Properties

You use certain properties in the TBLPROPERTIES clause of a Hive query that specifies the Kafka storage handler.

Property	Description	Required	Default
kafka.topic	Kafka topic name to map the table to	Yes	null
kafka.bootstrap.servers	Table property indicating the Kafka broker connection string	Yes	null
kafka.serde.class	Serializer and Deserializer class implementation	No	org.apache.hadoop.hive.serde2.JsonSerDe
hive.kafka.poll.timeout.ms	Parameter indicating Kafka Consumer poll timeout period in milliseconds. (This is independent of internal Kafka consumer timeouts.)	No	5000 (5 Seconds)
hive.kafka.max.retries	Number of retries for Kafka metadata fetch operations	No	6
hive.kafka.metadata.poll.timeout.ms	Number of milliseconds before consumer timeout on fetching Kafka metadata	No	30000 (30 Seconds)
kafka.write.semantic	Writer semantic with allowed values of NONE, AT_LEAST_ONCE, EXACTLY_ONCE	No	AT_LEAST_ONCE

Connecting Hive to BI tools using a JDBC/ODBC driver

To query, analyze, and visualize data stored in CDP, you use drivers provided by Cloudera to connect Apache Hive to Business Intelligence (BI) tools.

About this task

How you connect to Hive depends on a number of factors: the location of Hive inside or outside the cluster, the HiveServer deployment, the type of transport, transport-layer security, and authentication. HiveServer is the server interface that enables remote clients to run queries against Hive and retrieve the results using a JDBC or ODBC connection.

Before you begin

- Choose a Hive authorization model.
- Configure authenticated users for querying Hive through JDBC or ODBC driver. For example, set up a Ranger policy.

Getting the JDBC or ODBC driver in Data Hub

You need to download the Cloudera Hive JDBC or ODBC driver to your Data Hub cluster and provide it to your client. In the BI tool on the client's cluster, you need to provide the HiveServer (HS2) host name portion of the JDBC URL. The BI tool requires this information to connect to Hive in CDP.

Procedure

1. Download the JDBC or ODBC driver from the [Cloudera Downloads page](#).
2. Follow instructions in the documentation to install the driver on the same downloads page.

Integrating Hive and a BI tool


After you download an ODBC driver or a JDBC driver and give it to your client, you need to provide the information that the BI tool requires to connect to Hive in CDP.

Before you begin

You have downloaded the JDBC or ODBC driver.

Procedure

1. Depending on the type of driver you obtain, proceed as follows:
 - ODBC driver: follow instructions on the ODBC driver download site, and skip the rest of the steps in this procedure.
 - JDBC driver: add the driver to the classpath of your JDBC client. For example, check the client documentation about where to put the driver.
2. In Cloudera Manager (CM), click **Clusters** **Hive** click **Actions**, and select **Download Client Configuration**.



3. Unpack `hive_on_tez-clientconfig.zip`, open `beeline-site.xml`, and copy the value of `beeline.hs2.jdbc.url.hive_on_tez`. This value is the JDBC URL.
For example

```
jdbc:hive2://my_hiveserver.com:2181/;serviceDiscoveryMode=zooKeeper; \
zooKeeperNamespace=hiveserver2
```

4. In the BI tool, configure the JDBC connection using the JDBC URL and driver class name, `com.cloudera.hive.jdbc.HS2Driver`.