

Securing Apache Impala

Date published: 2019-11-01

Date modified: 2021-06-08



Legal Notice

© Cloudera Inc. 2024. All rights reserved.

The documentation is and contains Cloudera proprietary information protected by copyright and other intellectual property rights. No license under copyright or any other intellectual property right is granted herein.

Unless otherwise noted, scripts and sample code are licensed under the Apache License, Version 2.0.

Copyright information for Cloudera software may be found within the documentation accompanying each component in a particular release.

Cloudera software includes software from various open source or other third party projects, and may be released under the Apache Software License 2.0 (“ASLv2”), the Affero General Public License version 3 (AGPLv3), or other license terms. Other software included may be released under the terms of alternative open source licenses. Please review the license and notice files accompanying the software for additional licensing information.

Please visit the Cloudera software product page for more information on Cloudera software. For more information on Cloudera support services, please visit either the Support or Sales page. Feel free to contact us directly to discuss your specific needs.

Cloudera reserves the right to change any products at any time, and without notice. Cloudera assumes no responsibility nor liability arising from the use of products, except as expressly agreed to in writing by Cloudera.

Cloudera, Cloudera Altus, HUE, Impala, Cloudera Impala, and other Cloudera marks are registered or unregistered trademarks in the United States and other countries. All other trademarks are the property of their respective owners.

Disclaimer: EXCEPT AS EXPRESSLY PROVIDED IN A WRITTEN AGREEMENT WITH CLOUDERA, CLOUDERA DOES NOT MAKE NOR GIVE ANY REPRESENTATION, WARRANTY, NOR COVENANT OF ANY KIND, WHETHER EXPRESS OR IMPLIED, IN CONNECTION WITH CLOUDERA TECHNOLOGY OR RELATED SUPPORT PROVIDED IN CONNECTION THEREWITH. CLOUDERA DOES NOT WARRANT THAT CLOUDERA PRODUCTS NOR SOFTWARE WILL OPERATE UNINTERRUPTED NOR THAT IT WILL BE FREE FROM DEFECTS NOR ERRORS, THAT IT WILL PROTECT YOUR DATA FROM LOSS, CORRUPTION NOR UNAVAILABILITY, NOR THAT IT WILL MEET ALL OF CUSTOMER’S BUSINESS REQUIREMENTS. WITHOUT LIMITING THE FOREGOING, AND TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, CLOUDERA EXPRESSLY DISCLAIMS ANY AND ALL IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, QUALITY, NON-INFRINGEMENT, TITLE, AND FITNESS FOR A PARTICULAR PURPOSE AND ANY REPRESENTATION, WARRANTY, OR COVENANT BASED ON COURSE OF DEALING OR USAGE IN TRADE.

Contents

| | |
|--|----------|
| Securing Impala..... | 4 |
| Configuring Impala TLS/SSL..... | 5 |
| Impala Authentication..... | 6 |
| Configuring Kerberos Authentication..... | 6 |
| Configuring LDAP Authentication..... | 7 |
| Impala Authorization..... | 10 |
| Configuring Authorization..... | 16 |

Securing Impala

You must be aware of this set of security features Impala provides to protect your critical and sensitive data.

The Impala security features have several objectives.

- At the basic level, security prevents accidents or mistakes that could disrupt application processing, delete or corrupt data, or reveal data to unauthorized users.
- Advanced security features and practices can harden the system against malicious users trying to gain unauthorized access or perform other disallowed operations.
- The auditing feature provides a way to confirm that no unauthorized access occurred, and detect whether any such attempts were made.

Based on the above objectives, Impala security features are divided into the following categories.

Authentication

How does Impala verify the identity of the user to confirm that they really are allowed to exercise the privileges assigned to that user? Impala relies on the Kerberos subsystem for authentication.

Authorization

Which users are allowed to access which resources, and what operations are they allowed to perform? Impala relies on the open source Ranger project for authorization. By default (when authorization is not enabled), Impala does all read and write operations with the privileges of the `impala` user, which is suitable for a development/test environment but not for a secure production environment. When authorization is enabled, Impala uses the OS user ID of the user who runs `impala-shell` or other client program, and associates various privileges with each user.

TLS/SSL Encryption

This feature encrypts TLS/SSL network encryption, between Impala and client programs, and between the Impala-related daemons running on different nodes in the cluster.

Auditing

What operations were attempted, and did they succeed or not? This feature provides a way to look back and diagnose whether attempts were made to perform unauthorized operations. You use this information to track down suspicious activity, and to see where changes are needed in authorization policies. The audit data produced by this feature is collected by the Cloudera Manager product and then presented in a user-friendly form by the Cloudera Manager product.

The following are the important guidelines to protect a cluster running Impala against accidents and mistakes, or malicious attackers trying to access sensitive data. See the subsequent topics that describe the security features in detail.

- Secure the root account. The root user can tamper with the `impalad` daemon, read and write the data files in HDFS, log into other user accounts, and access other system services that are beyond the control of Impala.
- Restrict membership in the sudoers list (in the `/etc/sudoers` file). The users who can run the `sudo` command can do many of the same things as the root user.
- Ensure the Hadoop ownership and permissions for Impala data files are restricted.

The Impala authorization feature makes use of the HDFS file ownership and permissions mechanism.

1. Set up users and assign them to groups at the OS level, corresponding to the different categories of users with different access levels for various databases, tables, and HDFS locations (URIs).
 2. Create the associated Linux users using the `useradd` command if necessary.
 3. Add Linux users to the appropriate groups with the `usermod` command.
- Ensure the Hadoop ownership and permissions for Impala log files are restricted.

If you issue queries containing sensitive values in the `WHERE` clause, such as financial account numbers, those values are stored in Impala log files in the Linux file system, and you must secure those files.

- Ensure that the Impala web UI (available by default on port 25000 on each Impala node) is password-protected.
- Create a policy file that specifies which Impala privileges are available to users in particular Hadoop groups (which by default map to Linux OS groups). Create the associated Linux groups using the `groupadd` command if necessary.
- Design your databases, tables, and views with database and table structure to allow policy rules to specify simple, consistent rules.

For example, if all tables related to an application are inside a single database, you can assign privileges for that database and use the `*` wildcard for the table name. If you are creating views with different privileges than the underlying base tables, you might put the views in a separate database so that you can use the `*` wildcard for the database containing the base tables, while specifying the specific names of the individual views.

- Enable authorization for all `impalad` daemons.

The authorization feature does not apply to the `statedored` daemon, which has no access to schema objects or data files.

- Set up authentication using Kerberos, to make sure users really are who they say they are.

Related Information

[Configuring Impala Web UI](#)

Configuring Impala TLS/SSL

To protect sensitive information being transmitted, Impala supports TLS/SSL network encryption, between Impala and client programs, and between the Impala-related daemons running on different nodes in the cluster.

To configure Impala to listen for Beeswax and HiveServer2 requests on TLS/SSL-secured ports:

1. In Cloudera Manager, select the Impala service from the Clusters drop down.
2. In the Configuration tab, select ScopeImpala (Service-Wide).
3. Select CategorySecurity.
4. Edit the following property fields:

| Property | Description |
|---|--|
| Enable TLS/SSL for Impala | Encrypt communication between clients (like ODBC, JDBC, and the Impala shell) and the Impala daemon using Transport Layer Security (TLS) (formerly known as Secure Socket Layer (SSL)). |
| Impala TLS/SSL Server Certificate File (PEM Format) | Local path to the X509 certificate that identifies the Impala daemon to clients during TLS/SSL connections. This file must be in PEM format. |
| Impala TLS/SSL Server Private Key File (PEM Format) | Local path to the private key that matches the certificate specified in the Certificate for Clients. This file must be in PEM format. |
| Impala TLS/SSL Private Key Password | The password for the private key in the Impala TLS/SSL Server Certificate and Private Key file. If left blank, the private key is not protected by a password. |
| Impala TLS/SSL CA Certificate | The location on disk of the certificate, in PEM format, used to confirm the authenticity of SSL/TLS servers that the Impala daemons might connect to. Because the Impala daemons connect to each other, this should also include the CA certificate used to sign all the SSL/TLS Certificates. Without this parameter, SSL/TLS between Impala daemons will not be enabled. |

Using TLS/SSL with Business Intelligence Tools

You can use Kerberos authentication, TLS/SSL encryption, or both to secure connections from JDBC and ODBC applications to Impala.

Configuring TLS/SSL Communication for the Impala Shell

Typically, a client program has corresponding configuration properties in Cloudera Manager to verify that it is connecting to the right server. For example, with SSL enabled for Impala, you use the following options when starting the `impala-shell` interpreter:

- `--ssl`: enables TLS/SSL for `impala-shell`.
- `--ca_cert`: the local pathname pointing to the third-party CA certificate, or to a copy of the server certificate for self-signed server certificates.

If `--ca_cert` is not set, `impala-shell` enables TLS/SSL, but does not validate the server certificate. This is useful for connecting to a known-good Impala that is only running over TLS/SSL, when a copy of the certificate is not available (such as when debugging customer installations).

For `impala-shell` to successfully connect to an Impala cluster that has the minimum allowed TLS/SSL version set to 1.2 (`--ssl_minimum_version=tlsv1.2`), the cluster that `impala-shell` runs on must have Python version 2.7.9 or higher (or a vendor-provided Python version with the required support. Some vendors patched Python 2.7.5 versions on Red Hat Enterprise Linux 7 and derivatives).

Specifying TLS/SSL Minimum Allowed Version and Ciphers

Depending on your cluster configuration and the security practices in your organization, you might need to restrict the allowed versions of TLS/SSL used by Impala. Older TLS/SSL versions might have vulnerabilities or lack certain features. You can use startup options for the `impalad`, `catalogd`, and `statestored` daemons to specify a minimum allowed version of TLS/SSL.

Specify one of the following values for the `--ssl_minimum_version` configuration setting:

- `tlsv1`: Allow any TLS version of 1.0 or higher. This setting is the default when TLS/SSL is enabled.
- `tlsv1.1`: Allow any TLS version of 1.1 or higher.
- `tlsv1.2`: Allow any TLS version of 1.2 or higher.

Along with specifying the version, you can also specify the allowed set of TLS ciphers by using the `--ssl_cipher_list` configuration setting. The argument to this option is a list of keywords, separated by colons, commas, or spaces, and optionally including other notation. For example:

```
--ssl_cipher_list="RC4-SHA,RC4-MD5"
```

By default, the cipher list is empty, and Impala uses the default cipher list for the underlying platform. See the output of `man ciphers` for the full set of keywords and notation allowed in the argument string.

Impala Authentication

Authentication is the mechanism to ensure that only specified hosts and users can connect to Impala.

Authentication feature verifies that when clients connect to Impala, they are connected to a legitimate server. The feature prevents spoofing such as *impersonation* (setting up a phony client system with the same account and group names as a legitimate user) and *person-in-the-middle attacks* (intercepting application requests before they reach Impala and eavesdropping on sensitive information in the requests or the results).

Impala automatically handles both Kerberos and LDAP authentication. Each `impalad` daemon can accept both Kerberos and LDAP requests through the same port. No special actions need to be taken if some users authenticate through Kerberos and some through LDAP.

You can also make proxy connections to Impala through Apache Knox.

Regardless of the authentication mechanism used, Impala always creates HDFS directories and data files owned by the same user (typically `impala`). Once you are finished setting up authentication, set up authorization to control user-level access to databases, tables, columns, partitions when they connect through Impala.

Configuring Kerberos Authentication

Impala supports an enterprise-grade authentication system called Kerberos. Kerberos provides strong security benefits including capabilities that render intercepted authentication packets unusable by an attacker. It virtually eliminates the threat of impersonation by never sending a user's credentials in cleartext over the network.

Requirements for Using Impala with Kerberos



Important:

- If you plan to use Impala in your cluster, you must configure your KDC to allow tickets to be renewed, and you must configure `krb5.conf` to request renewable tickets. Typically, you can do this by adding the `max_renewable_life` setting to your realm in `kdc.conf`, and by adding the `renew_lifetime` parameter to the `libdefaults` section of `krb5.conf`.

Impala supports the Cloudera ODBC driver and the Kerberos interface provided. To use Kerberos through the ODBC driver, the host type must be set depending on the level of the ODBC driver:

- SecImpala for the ODBC 1.0 driver.
- SecBeeswax for the ODBC 1.2 driver.
- Blank for the ODBC 2.0 driver or higher, when connecting to a secure cluster.
- HS2NoSasl for the ODBC 2.0 driver or higher, when connecting to a non-secure cluster.

Enabling Kerberos in Impala-shell

To enable Kerberos in the Impala shell, start the `impala-shell` command using the `-k` flag.

Configuring Impala to Support Kerberos Security

Enabling Kerberos authentication for Impala involves steps that can be summarized as follows:

- Creating service principals for Impala and the HTTP service. Principal names take the form: *serviceName/fully.qualified.domain.name@KERBEROS.REALM*
- Creating, merging, and distributing key tab files for these principals.
- Editing `/etc/default/impala` (in cluster not managed by Cloudera Manager), or editing the Security settings in the Cloudera Manager interface, to accommodate Kerberos authentication.

Enabling Access to Internal Impala APIs for Kerberos Users

For applications that need direct access to Impala APIs, without going through the HiveServer2 or Beeswax interfaces, you can specify a list of Kerberos users who are allowed to call those APIs. By default, the `impala` and `hdfs` users are the only ones authorized for this kind of access. Any users not explicitly authorized through the internal `_principals_whitelist` configuration setting are blocked from accessing the APIs. This setting applies to all the Impala-related daemons, although currently it is primarily used for HDFS to control the behavior of the catalog server.

Mapping Kerberos Principals to Short Names for Impala

Impala can support the additional mapping rules that will be inserted before rules generated from the list of trusted realms and before the default rule. The support is disabled by default in Impala.

To enable mapping Kerberos principals to short names:

1. In Cloudera Manager, select the Impala service.
2. In the Configuration tab, select Impala (Service-Wide) in Scope and Advanced in Category.
3. Select the Use HDFS Rules to Map Kerberos Principals to Short Names field.
4. Click Save Changes, and restart the Impala service.

Configuring LDAP Authentication

Impala uses LDAP for authentication, verifying the credentials of each user who connects through `impala-shell`, Hue, a Business Intelligence tool, JDBC or ODBC applications.

About this task

Authentication is the process of allowing only specified named users to access the server (in this case, the Impala server). This feature is crucial for any production deployment, to prevent misuse, tampering, or excessive load on the server.

Only the connections between clients and Impala can be authenticated by LDAP.

Procedure

To enable and configure LDAP:

1. In Cloudera Manager, select the Impala service.
2. In the Configuration tab, type `ldap` in the search box. The fields for LDAP configuration will be listed.
3. Set the following fields to enable LDAP.

Enable LDAP Authentication (`enable_ldap_auth`)

Enables LDAP-based authentication between the client and Impala.

LDAP URL (`ldap_uri`)

Sets the URI of the LDAP server to use. Typically, the URI is prefixed with `ldap://`. You can specify secure SSL-based LDAP transport by using the prefix `ldaps://`. The URI can optionally specify the port, for example: `ldap://ldap_server.example.com:389` or `ldaps://ldap_server.example.com:636`. (389 and 636 are the default ports for non-SSL and SSL LDAP connections, respectively.)

4. Set the following fields to support custom bind strings.

When Impala connects to LDAP, it issues a bind call to the LDAP server to authenticate as the connected user. Impala clients, including the Impala-shell, provide the short name of the user to Impala. This is necessary so that Impala can use role-based access, which uses short names.

However, LDAP servers often require more complex, structured usernames for authentication. Impala supports three ways of transforming the short name (for example, 'henry') to a more complicated string. If necessary, specify one of the following configuration options when starting the `impalad` daemon.

Active Directory Domain (`--ldap_domain`)

Replaces the username with a string `username@ldap_domain`.

LDAP BaseDN (`--ldap_baseDN`)

Replaces the username with a “distinguished name” (DN) of the form: `uid=userid,ldap_baseDN`. (This is equivalent to a Hive option).

LDAP Pattern (`--ldap_bind_pattern`)

This is the most general option, and replaces the username with the string `ldap_bind_pattern` where all instances of the string `#UID` are replaced with `userid`. For example, an `ldap_bind_pattern` of `"user=#UID,OU=foo,CN=bar"` with a username of `henry` will construct a bind name of `"user=henry,OU=foo,CN=bar"`.

The above options are mutually exclusive, and Impala does not start if more than one of these options are specified.

5. Set the following fields for secure LDAP connections.

To avoid sending credentials over the wire in cleartext, you must configure a secure connection between both the client and Impala, and between Impala and the LDAP server. The secure connection could use SSL or TLS.

Secure LDAP connections through SSL:

For SSL-enabled LDAP connections, specify a prefix of `ldaps://` instead of `ldap://`. Also, the default port for SSL-enabled LDAP connections is 636 instead of 389.

Secure LDAP connections through TLS:

TLS, the successor to the SSL protocol, is supported by most modern LDAP servers. Unlike SSL connections, TLS connections can be made on the same server port as non-TLS connections. To secure all connections using TLS, specify the following flags as startup options to the `impalad` daemon:

Enable LDAP TLS (`--ldap_tls_`

Tells Impala to start a TLS connection to the LDAP server, and to fail authentication if it cannot be done.

LDAP Server CA Certificate (`--ldap_ca_certificate`)

Specifies the location of the certificate in standard .PEM format. Store this certificate on the local filesystem, in a location that only the `impala` user and other trusted users can read.

6. Click Save Changes and restart the Impala service.

Enabling LDAP in Hue

To connect to Impala using LDAP authentication through Hue, enable the LDAP setting in Hue.

Procedure

1. Go to the Hue service.
2. Click the Configuration tab.
3. Select ScopeHue Server.
4. Select CategoryAdvanced.
5. Add the following properties to the Hue Server Advanced Configuration Snippet (Safety Valve) for `hue_safety_valve_server.ini` property

```
[impala]
auth_username=<LDAP username of Hue user to be authenticated>
auth_password=<LDAP password of Hue user to be authenticated>
```

6. Click Save Changes.

Enabling LDAP Authentication for `impala-shell`

To connect to Impala using LDAP authentication, you specify command-line options to the `impala-shell` command interpreter and enter the password when prompted.

-l

Enables LDAP authentication.

-u

Sets the user. Per Active Directory, the user is the short username, not the full LDAP distinguished name. If your LDAP settings include a search base, use the `--ldap_bind_pattern` on the `impalad` daemon to translate the short user name from `impala-shell` automatically to the fully qualified name.

`impala-shell` automatically prompts for the password.

Impala Authorization

Authorization determines which users are allowed to access which resources, and what operations they are allowed to perform. You use Apache Ranger to enable and manage authorization in Impala.

Supported Ranger Features in Impala


- Resource-based and tag-based authorization policies
- Resource-based and tag-based column masking

Unsupported Ranger Features in Impala

- Row-level filtering

Using Resource-based Authorization Policies for Impala

In the Ranger Service Manager, you can use the Hadoop SQL preloaded resource-based and tag-based services and policies to authorize access to Impala:



You can configure services for Impala as described in [Using Ranger to Provide Authorization in CDP](#).

For example, you can edit the all-global policy for an Impala user:



For information about using tag-based policies, see [Tag-based column masking in Hive with Ranger policies](#).

Privilege Model

You set up privileges through the GRANT and REVOKE statements in either Impala or Hive. Then both components use those same privileges automatically.

By default, when authorization is not enabled, Impala does all read and write operations with the privileges of the `impala` user, which is suitable for a development/test environment but not for a secure production environment. When authorization is enabled, Impala uses the OS user ID of the user who runs `impala-shell` or other client programs, and associates various privileges with each user.

Privileges can be granted on different resources in the schema and are associated with a level in the resource hierarchy. A privilege on a particular resource automatically inherits the same privilege of its parent.

The resource hierarchy is:

```

Server
  URI
  Database
    Table
      Column
      Function

```

The table-level privileges apply to views as well. Anywhere you specify a table name, you can specify a view name instead.

You can specify privileges for individual columns.

The table below lists the minimum level of privileges and the scope required to run SQL statements in Impala. The following notations are used:

- The SERVER resource type in Ranger implies all databases, all tables, all columns, all UDFs, and all URLs.
- ANY denotes the CREATE, ALTER, DROP, SELECT, INSERT, or REFRESH privilege.
- ALL privilege denotes the SELECT, INSERT, CREATE, ALTER, DROP, and REFRESH privileges.
- VIEW_METADATA privilege denotes the SELECT, INSERT, or REFRESH privileges.
- The parent levels of the specified scope are implicitly supported. For example, if a privilege is listed with the TABLE scope, the same privilege granted on DATABASE and SERVER will allow the user to run that specific SQL statement on TABLE.



Note: For an "impala" user to access any managed tables under the warehouse root directory or external tables with directories outside the warehouse root directory, the "impala" user must have HDFS RW access to the underlying paths that are referenced in a query.

For example, to be able to run CREATE VIEW, you need the CREATE privilege on the database and the SELECT privilege on the source table.

| SQL Statement | Privileges | Object Type / Resource Type |
|--------------------------|------------|-----------------------------|
| SELECT | SELECT | TABLE |
| WITH SELECT | SELECT | TABLE |
| EXPLAIN SELECT | SELECT | TABLE |
| INSERT | INSERT | TABLE |
| EXPLAIN INSERT | INSERT | TABLE |
| TRUNCATE | INSERT | TABLE |
| LOAD | INSERT | TABLE |
| | ALL | URI |
| CREATE DATABASE | CREATE | SERVER |
| CREATE DATABASE LOCATION | CREATE | SERVER |

| | | |
|--------------------------------|----------------|----------|
| | ALL | URI |
| CREATE TABLE | CREATE | DATABASE |
| CREATE TABLE LIKE | CREATE | DATABASE |
| | VIEW_METADATA | TABLE |
| CREATE TABLE AS SELECT | CREATE | DATABASE |
| | INSERT | DATABASE |
| | SELECT | TABLE |
| EXPLAIN CREATE TABLE AS SELECT | CREATE | DATABASE |
| | INSERT | DATABASE |
| | SELECT | TABLE |
| CREATE TABLE LOCATION | CREATE | TABLE |
| | ALL | URI |
| CREATE VIEW | CREATE | DATABASE |
| | SELECT | TABLE |
| ALTER DATABASE SET OWNER | ALL WITH GRANT | DATABASE |
| ALTER TABLE | ALL | TABLE |
| ALTER TABLE SET LOCATION | ALL | TABLE |
| | ALL | URI |
| ALTER TABLE RENAME | CREATE | DATABASE |
| | ALL | TABLE |
| ALTER TABLE SET OWNER | ALL WITH GRANT | TABLE |
| ALTER VIEW | ALL | TABLE |
| | SELECT | TABLE |
| ALTER VIEW RENAME | CREATE | DATABASE |
| | ALL | TABLE |
| ALTER VIEW SET OWNER | ALL WITH GRANT | VIEW |
| DROP DATABASE | ALL | DATABASE |
| DROP TABLE | ALL | TABLE |
| DROP VIEW | ALL | TABLE |
| CREATE FUNCTION | CREATE | DATABASE |
| | ALL | URI |
| DROP FUNCTION | ALL | DATABASE |
| COMPUTE STATS | ALL | TABLE |
| DROP STATS | ALL | TABLE |
| INVALIDATE METADATA | REFRESH | SERVER |
| INVALIDATE METADATA <table> | REFRESH | TABLE |
| REFRESH <table> | REFRESH | TABLE |
| REFRESH AUTHORIZATION | REFRESH | SERVER |
| REFRESH FUNCTIONS | REFRESH | DATABASE |
| COMMENT ON DATABASE | ALL | DATABASE |

| | | |
|---|---------------|----------|
| COMMENT ON TABLE | ALL | TABLE |
| COMMENT ON VIEW | ALL | TABLE |
| COMMENT ON COLUMN | ALL | TABLE |
| DESCRIBE DATABASE | VIEW_METADATA | DATABASE |
| DESCRIBE <table/view> | VIEW_METADATA | TABLE |
| If the user has the SELECT privilege at the COLUMN level, only the columns the user has access will show. | SELECT | COLUMN |
| USE | ANY | TABLE |
| SHOW DATABASES | ANY | TABLE |
| SHOW TABLES | ANY | TABLE |
| SHOW FUNCTIONS | VIEW_METADATA | DATABASE |
| SHOW PARTITIONS | VIEW_METADATA | TABLE |
| SHOW TABLE STATS | VIEW_METADATA | TABLE |
| SHOW COLUMN STATS | VIEW_METADATA | TABLE |
| SHOW FILES | VIEW_METADATA | TABLE |
| SHOW CREATE TABLE | VIEW_METADATA | TABLE |
| SHOW CREATE VIEW | VIEW_METADATA | TABLE |
| SHOW CREATE FUNCTION | VIEW_METADATA | DATABASE |
| SHOW RANGE PARTITIONS (Kudu only) | VIEW_METADATA | TABLE |
| UPDATE (Kudu only) | ALL | TABLE |
| EXPLAIN UPDATE (Kudu only) | ALL | TABLE |
| UPSERT (Kudu only) | ALL | TABLE |
| WITH UPSERT (Kudu only) | ALL | TABLE |
| EXPLAIN UPSERT (Kudu only) | ALL | TABLE |
| DELETE (Kudu only) | ALL | TABLE |
| EXPLAIN DELETE (Kudu only) | ALL | TABLE |

The privileges not listed in the table above will be silently ignored by Impala.

Changing Privileges in Impala

Privileges are managed via the GRANT and REVOKE SQL statements that require the Ranger service enabled.

Privileges can be also managed in Ranger UI. Especially, for attribute-based access control, Ranger UI is required to manage authorization.

Impala authorization policies are listed in the Hive service section in Ranger UI.

REFRESH AUTHORIZATION is not required when you make the changes to privileges within Impala. The changes are automatically propagated.

Changing Privileges from Outside of Impala

If you make a change to privileges in Ranger from outside of Impala, e.g. adding a user, removing a user, modifying privileges, there are two options to propagate the change:

- Use the ranger.plugin.hive.policy.pollIntervalMs property to specify how often to do a Ranger refresh. The property is specified in ranger-impala-security.xml in the conf directory under your Impala home directory.

- Run the REFRESH AUTHORIZATION statement to force a refresh.



Warning: As INVALIDATE METADATA is an expensive operation, you should use it judiciously.

Granting Privileges on URI

URIs represent the file paths you specify as part of statements such as CREATE EXTERNAL TABLE and LOAD DATA. Typically, you specify what look like UNIX paths, but these locations can also be prefixed with hdfs:// to make clear that they are really URIs. To set privileges for a URI, specify the name of a directory, and the privilege applies to all the files in that directory and any directories underneath it.

URIs must start with hdfs://, s3a://, adl://, or file://. If a URI starts with an absolute path, the path will be appended to the default filesystem prefix. For example, if you specify:

```
GRANT ALL ON URI '/tmp' ;
```

The above statement effectively becomes the following where the default filesystem is HDFS.

```
GRANT ALL ON URI 'hdfs://localhost:20500/tmp' ;
```

When defining URIs for HDFS, you must also specify the NameNode. For example:

```
GRANT ALL ON URI file:///path/to/dir TO <principal>
GRANT ALL ON URI hdfs://namenode:port/path/to/dir TO <principal>
```



Warning: Because the NameNode host and port must be specified, it is strongly recommended that you use High Availability (HA). This ensures that the URI will remain constant even if the NameNode changes. For example:

```
GRANT ALL ON URI hdfs://ha-nn-uri/path/to/dir TO <principal>
```



Note:

<principal> can be a user, or a group



Note:

- If a user uses Impala SQL engine to access the resource of the specified URL/URI provided as part of the SQL statement and as an admin if you must deny access permissions to this location for this particular user, you must add the permission "All" in the "HADOOP SQL" policy.
- However, if the user is using Hive as the execution engine and to deny access permission to a location, then you must add both the "Read" and "Write" permissions in the field of 'Permissions' for the corresponding deny conditions.
- If the same Ranger policy is shared by both Hive and Impala, then you must add "All", "Read", and "Write" to the field of 'Permissions' to enforce the policy.

Object Ownership

Object ownership for tables, views and databases is enabled by default in Impala.

To define owner specific privileges, go to Ranger UI and define appropriate policies on the {OWNER} user.

The CREATE statements implicitly make the user running the statement the owner of the object. For example, if *User A* creates a database, *foo*, via the CREATE DATABASE statement, *User A* now owns the *foo* database and is authorized to perform any operation on the *foo* database.

An ownership can be transferred to another user or role via the ALTER DATABASE, ALTER TABLE, or ALTER VIEW with the SET OWNER clause.



Note: Currently, due to a known issue ([IMPALA-8937](#)), until the ownership information is fully loaded in the coordinator catalog cache, the owner of a table might not be able to see the table when executing the SHOW TABLES statement. The owner can still query the table.

Ranger Column Masking for Impala

Ranger column masking hides sensitive columnar data in Impala query output. For example, you can define a policy that reveals only the first or last four characters of column data. Column masking is enabled by default. To disable column masking, modify the following configuration property in all coordinators:

```
--enable_column_masking=false
```

This flag might be removed in a future release. The Impala behavior mimics Hive behavior with respect to column masking.

The following table lists all Impala-supported, built-in mask types for defining column masking in a policy using the Ranger REST API or Ranger UI:

| Type | Name | Description | Transformer |
|---------------------|----------------------------------|---|---|
| MASK | Redact | Replace lowercase with 'x', uppercase with 'X', digits with '0' | mask({col}) |
| MASK_SHOW_LAST_4 | Partial mask: show last 4 | Show last 4 characters; replace rest with 'x' | mask_show_last_n({col}, 4, 'x', 'x', 'x', -1, '1') |
| MASK_SHOW_FIRST_4 | Partial mask: show first 4 | Show first 4 characters; replace rest with 'x' | mask_show_first_n({col}, 4, 'x', 'x', 'x', -1, '1') |
| MASK_HASH | Hash | Hash the value | mask_hash({col}) |
| MASK_NULL | Nullify | Replace with NULL | N/A |
| MASK_NONE | Unmasked (retain original value) | No masking | N/A |
| MASK_DATE_SHOW_YEAR | Date: show only year | Date: show only year | mask({col}, 'x', 'x', 'x', -1, '1', 1, 0, -1) |
| CUSTOM | Custom | Custom | N/A |

The table includes the mask name as it appears in the Ranger UI.

Select Masking Option

☐ Redact
 ☐ Partial mask: show last 4
 ☐ Partial mask: show first 4
 ☐ Hash
 ☐ Nullify
 ☐ Unmasked (retain original value)
 ☐ Date: show only year
 ☐ Custom

☒ ☐

Ranger Column Masking Limitations in Impala

- Column masking introduces unused columns during the query analysis and, consequently, additional SELECT privileges checks on all columns of the masked table.
- Impala might produce more than one audit log entry for a column involved in a column masking policy under all of these conditions: the column appears in multiple places in a query, the query is rewritten, or the query is re-analyzed.
- Column masking policies, shared between Hive and Impala, might be affected by SQL/UDF differences between Hive and Impala, as shown in the following example.

For instance, UTF-8 strings containing non-ASCII characters are not guaranteed to work properly. Suppose a column masking policy masks the last two characters of a string: `s => mask_last_n(s, 2, 'x', 'x', 'x', 'x')`. Applying this policy, Hive properly masks `SQL##` to `SQLxx`, but the Impala masking produces `SQL##xx` because each Chinese character is encoded in 3 bytes. Impala and Hive do not handle different lengths in the same way.

Limitations on Mask Functions

The mask functions in Hive are implemented through GenericUDFs. Even though Impala users can call Hive UDFs, Impala does not yet support Hive GenericUDFs, so you cannot use Hive's mask functions in Impala. However, Impala has builtin mask functions that are implemented through overloads. In Impala, when using mask functions, not all parameter combinations are supported. These mask functions are introduced in Impala 3.4

The following list includes all the implemented overloads.

- Overloads used by Ranger default masking policies,
- Overloads with simple arguments,
- Overload with all arguments in int type for full functionality. Char argument needs to be converted to their ASCII value.

To list the available overloads, use the following query:

```
show functions in _impala_builtins like "mask*";
```



Note: An error message that states "No matching function with signature: mask..." implies that Impala does not contain the corresponding overload.

Related Information

[GRANT statement](#)

[REVOKE statement](#)

[Resource-based column masking in Hive with Ranger policies](#)

[Tag-based column masking in Hive with Ranger policies](#)

[Apache Ranger documentation](#)

Configuring Authorization

Enable Ranger authorization in Impala.

Procedure

1. In Cloudera Manager, navigate to the Impala service.
2. In the Configuration tab, type ranger in the search field.

3. Specify the values in the following fields.

- Ranger Service: Select the Ranger service you are using. This is the server name to use when granting server level privileges.
- Ranger Policy Cache Directory: Specify the directory where Ranger security policies are cached locally.
- Ranger DFS Audit Path: Specify the DFS path on which Ranger audits are written. The special placeholder `'${ranger_base_audit_url}'` should be used as the prefix, in order to use the centralized location defined in the Ranger service.
- Ranger Audit DFS Spool Dir: Specify the spool directory for Ranger audits being written to DFS.
- Ranger Audit Solr Spool Dir: Specify the spool directory for Ranger audits being written to Solr.

4. Restart Impala and Hive.